JULA 6 1001 1 10 NWC TP 7068

# User's Guide to the U.S. Navy Insensitive Munitions Information System Munition Status Information Center

by

Carolyn A. Dettling
Insensitive Munitions Office
Ordnance Systems Department

**DECEMBER 1990** 

## NAVAL WEAPONS CENTER CHINA LAKE, CA 93555-6001





Approved for public release

91-04944

91 7 7 9 0 3

# **Naval Weapons Center**

### **FOREWORD**

The Navy Insensitive Munitions Information System comprises three databases: Munitions Status Information Center (MSIC), Insensitive Munitions Engineering Technology (IMET), and Energetic Materials Information Center (EMIC). The MSIC has been designed to provide real-time status of Navy weapon response to IM testing. The IMET will provide real-time reporting of insensitive munitions (IM) technology, plans, prognoses, and progress. The EMIC will provide IM and performance-related properties of energetic materials. Explosives, propellants, and pyrotechnics will be included.

This document provides users with a "step-by-step" approach to access MSIC data. The programs to support the data files have been written in a user-friendly, menu-driven environment to allow non-computer-oriented professionals to access and manipulate the data.

This report has been reviewed for technical accuracy by John Fontenot, Code 3208.

Approved by D. A. GOSS, Acting Head Ordnance Systems Department 11 December 1990 Under authority of DOUGLAS W. COOK Capt., U.S. Navy Commander

Released for publication by W. B. PORTER
Technical Director

### **NWC Technical Publication 7068**

Published by	Technical Information Department
Collation	Cover, 37 leaves
First printing	65 copies

### REPORT DOCUMENTATION PAGE

Forn, Approved OMB No. 0704-0188

Public reporting burden for this collection of information is estimated to average 1 hour per response, including the time for reviewing instructions, searching existing data sources gathering and maintaining the data needed, and completing and reviewing the collection of information. Send comments regarding the burden estimate or any other aspect of this collection of information, including suggestions for reducing this burden, to Washington Headquarters Services. Directoriste for information Operations and Reports, 1215 Jefferson Davis Highway, Suite 1204, Arlington, VA 22202-4302, and to the Office of Management and Budget, Paperwork Reduction Project (0704-0188). Washington, DC 20503

mighway, Suite 1204, Arrington, VA 22202-4302, and	:::			
1. AGENCY USE ONLY (Leave blank			PE AND DATES	COVERED
	11 December 1990	Users Guide, 1	1989-1990	
4. TITLE AND SUBTITLE			5. FUNDII	NG NUMBERS
User's Guide to the U.S. Navy I		ation System	1	
Munition Status Information Ce				
6. AUTHOR(S)		<del></del>	1	
Carolyn A. Dettling			1	
7. PERFORMING ORGANIZATION N	AME(S) AND ADDRESS(ES)			RMING ORGANIZATION
Naval Weapons Center			REPOR NWC TP 76	I <b>T NUMBER</b> OGR
China Lake, CA 93555-6001			INWCIP?	UUO
			1	
9. SPONSORING/MONITORING AGI	ENCY NAME(S) AND ADDRESS(ES)			ORING/MONITORING
	_ , = =		AGEN	CYREPORT NUMBER
			1	
			1	
			<u></u>	
11. SUPPLEMENTARY NOTES		·	_ <del>_</del>	· · · · · · · · · · · · · · · · · · ·
12a. DISTRIBUTION/AVAILABILITY S	TATEMENY		125 niste	RIBUTION CODE
A Statement	***************		, 23. DISTA	
Sourcement			1	
			1	
			1	
13. ABSTRACT (Maximum 200 word	s)	<del></del>	<del></del>	
	ormation Center (MSIC) is a			
on munitions exposed to inser				
friendly, menu-driven environs				ess and manipulate the
data. This document is written	with a step-by-step approach	n to access the MS	iC data.	
14 CIBERT TERIAL			<del></del>	15. NUMBER OF PAGES
14. SUBJECT TERMS			1	15. NUMBER OF PAGES
A EPs, Aircraft Fuel Tanks, Air	craft Guns Air Launchod M	lissiles Rombe C	ADs.	
Fuzes, Mines, Pyrotechnics, Ro				16. PRICE CODE
	B. SECURITY CLASSIFICATION OF	19. SECURITY CLASS OF ABSTRACT	SIFICATION	20. LIMITATION OF ABSTRACT
OF REPORT	THIS PAGE	Unclassified	•	
Unclassified U	nclassified	Onciassified	1	

Angle Ang Angle Ang

, . ·		
( 100,	مرکزی	١
\ P'	SE /	•

Assension For	
AL' S GMAAL	N
BTIC TAB	Ü
operation wheed	Li
of actifications.	

or Arteution/

\* Pilosipaty Codes System of anotor

### CONTENTS

Introduction	5
Background	5
Munitions Status Information Center	6
Data Dictionary	8
Getting Started	9
Opening Screen	10
Selection of Program Options	11
[V] View Existing Data	12
Selection of Data	13
Accessing the Data Files	14
[T] Change Test	15
[L] Locate a Test	16
[S] Change Screen	17
General Test Information, Screen 2	18
Component Data, Screen 3	19
Test Data Reference for Test ID Number, Screen 4	20
[C] Change Diskette	22
	24
(P) Print Data	
Setting Filter Conditions	26
[1] Print Test Data	29
[2] Print Component Data	33
[S] Run Summary Program	39
[L] List or Locate	38
[1] List to Screen and [2] List to Printer	39
Field Selections for List Option	40
Setting Conditions for List	42
13  Locate a Record	49
Field Selections for Locate Option	49
Setting Conditions for Locate Option	51
[9] Time to Reaction	57
[8] Component Reaction	61
Classes of Reactions	62
Summary	69

Conclusio	ns	69
Inse	MIS Databases nsitive Munitions Engineering Technology (IMET) getic Materials Information Center (EMIC)	69 69 70
Reference	s	71
Figures:		
1b. 2. 3.	Elements of the Test ID Number  Elements of the Document Serial Number Initial Screen Opening Screen	7 9 10
<b>5</b> .	Main Menu Screen Selection of Data Screen	12 13
6b. 6c.	Test Screen 1 of 4 Screens Test screen 1 of 4 Screens Partial Test 11) Number Used to Locate Test Test Screen 2 of 4 Screens	14 15 16
8. 9.	Test Screen 2 of 4 Screens Test Screen 3 of 4 Screens Screen 4 of 4 Screens	18 19 20
10b.	Main Menu Screen Change Diskette Instructions Instructions Continued	22 22 23
11. 12.	Main Menu Screen	2.4 25
13b.	Prompt to Set Condition, Test Date Selection of Test Date	26 27 28
14a.	Final Prompt to Select Test Date Print Data Screen	28 29
15a.	Print Options Screen  Sample Screen of Available Test IDs for Printing  Sample Printed of Tests Date for Broads Warrant	30
16.	Sample Printout of Tests Data for Pseudo Weapon  Main Menu Screen  Print Data Screen	32 33 34
18. 19.	Print Options Screen	34 35
21. 22.	Sample Printouts of Component Data  Main Menu Screen  List or Locate Screen	37 38 39
23b.	Field Selection Screen for List Option  Field Selection Screen With One Selection Shown on Command Line  Field Selection Screen With Two Selections Shown on Command Line	40 41 41
23d.	Field Selection Screen With Three Selection Shown on Command Line Field Selection Screen With Conditions Prompt	42 42
	Condition Screen	43

	Example of List of Stimuli	44
25a.	Condition Screen	45
	Condition Screen With One Condition Selected	46
25c.	Condition Screen With Two Conditions Selected	46
25d.	Condition Screen With Final Approval Prompt	47
<b>26</b> .	Sample Listing of Pseudo Information	48
<b>27</b> .		49
28a.	Field Selection Screen for Locate a Record Option	50
28b.	Locate Screen with Enter Test Date Equality or Inequality Prompt	41
28c.	Locate Screen With "Less Than 1 January 1990" Entered	51
	Locate Screen With One Condition Selected	δŽ
<b>29</b> .	Field Selection Screen for Locate a Record Option	52
<b>30</b> .	List of Stimuli	53
31a.	Condition Screen, Conditions Set	54
31b.	Test Data Screen 1 of 4 Screens	55
31c.	Locate Continuation Prompt	56
32	List or Locate Screen	57
<b>33</b> .	Locate Option Screen	58
34a.	Condition Screen for Locate Option	58
34b.	Condition Selected	59
34c.	Condition Appears on Command Line	60
35a.	ı	61
	Value Selection Screen	62
35c.	Value Screen Prior to Use of "Enter" < RETURN > Key	63
35d.		
	Prior to Final Confirmation	63
35e.	Reaction Value Appears on Command Line of Condition Screen	64
36a.	Locate Screen With View Prompt	65
36b.	Test Screen 1 of 4 Screens, Test Data	66
	Test Screen 2 of 4 Screens, Test Discussion	<b>66</b>
	Test Screen 3 of 4 Screens, Component Data	67
36e.	Test Screen 4 of 4 Screens, Documentation Data	67

### **ACKNOWLEDGMENT**

The assistance, talents, and expertise of many individuals have been invaluable in the development of the MSIC computer program and the preparation of this document. The Insensitive Munitions Office appreciates the efforts of Patty Hardekopf (EG&G Washington Analytical Services Center, Inc.) for configuration management; Lynne Burke (Comarco, Inc.) for initial computer programming; Cindy Winberry (Comarco, Inc.) for debugging and maintaining the computer program and verifying the user documentation, Cathy Foisy (Comarco, Inc.) for entering data files and providing examples of computer screens and printouts; and Jeanette Mullis (NWC Code 3461) for the major effort of editing and rewriting, formatting, and composing the report.

### INTRODUCTION

The U.S. Navy Insensitive Munitions information System (NIMIS) Program was initiated because the profusion of data relating to the Navy's Insensitive Munitions (IM) program, although available, was widely scattered. The goal of the NIMIS Program has been to not only gather all obtainable IM-related material, but to incorporate it into a user-friendly, relational database that would allow easy manipulation of the data.

Programs have been written and refined to allow the entry and use of (1) weapon response to fast cookoff, slow cookoff, bullet impact, fragment impact, and sympathetic detonation testing, and (2) generic IM engineering development test results. The programs are usable with IBM, IBM compatible, and Macintosh sonal computers.

### BACKGROUND

U.S. Navy IM program policy was set by the Chief of Naval Operations in May 1984 (Reference 1) in response to a growing desire to improve the performance of weapons exposed to unplanned hazardous stimuli. On 22 May 1985, the technical requirements for IM were published by the Naval Sea Systems Command (NAVSEA) (Reference 2). Both documents have been updated since that time. As of this printing, References 3 and 4 are the latest iterations.

In accordance with Navy policy, all new Navy weapons are being developed to meet IM goals. Those already in the field or under development are also required to meet these objectives, with complete transition to an insensitive arsenal targeted for 1995. Fleet readiness and operational capability are to be maintained throughout this evolution.

Policy dictates that a munition shall respond with no more than a burning reaction to IM stimuli with the exception of the sympathetic detonation (SD) stimulus, in which case the munition shall not sympathetically detonate.

1M test procedures are described in several documents: fast cookoff (Reference 5), slow cookoff and bullet impact (Reference 6), and fragment impact (Reference 7). These procedures will be revised and clarified, then incorporated along with procedures for sympathetic detonation and safety testing in the latest revision of DOD-STD-2105 (Reference 8).

A burning reaction is defined as ignition and burning of a weapon's energetic material, mild release of combustion gases following melting or weakening of the warhead or rocket motor case due to thermal or impact stresses is allowed. Any debris must remain in the immediate area of the event, although case closures may be distudged by internal pressure and thrown up to about 50 feet. Beyond that distance, however, they must not be hazardous fragments, which are defined as those with an impact energy of greater than 58 ft-lb (79 joules).

Navy IM requirements are applicable to all munitions carried aboard Navy ships and aircraft no matter the source of design or manufacture, excluding strategic and nuclear weapons.

Technical coordination of the NIMIS Program undertaken by the Navy has been assigned to the Naval Weapons Center (NWC), China Lake, Calif. Two of the three databases proposed by NWC are nearing completion, and the third is currently under way.

The Navy IM Information System comprises three databases:

- 1. Munitions Status Information Center (MSIC)
- 2. Insensitive Munitions Engineering Technology (IMET)
- 3. Energetic Materials Information Center (EMIC)

The MSIC has been designed to provide real-time status of Navy weapon response to IM testing. The IMET will provide real-time reporting IM technology, plans, and progress. The EMIC will provide IM and performance-relevant properties of energetic materials. Explosives, propellants, and pyrotechnics will be included.

This document has been prepared specifically for the use of MSIC.

### MUNITIONS STATUS INFORMATION CENTER

The Munitions Status Information Center (MSIC) is a set of data files designed and organized to contain test information and results on munitions exposed to IM-related stimuli. A set of programs was written to support the data files in a user-friendly, menu-driven environment to allow non-computer-oriented professionals to access and manipulate the data. Presently, there are more than 1500 test records in the MSIC with additional entries incorporated each week. Fleet configurations for each weapon and its container(s) are provided.

Data groupings provide simple breakdowns of munition configurations: test setups, procedures, and results in both summary and field\* formats. Information notation in fields permits the use of fundamental search routines. Also included is bibliographic data reference information including a point of contact.

<sup>\*</sup> Field refers to a position in the computer that holds data.

The data in this system are entered into three separate data files: (1) general test data, (2) individual component data, and (3) reference data. The files are linked by an eight-character alphanumeric code unique to each test. The code is called the "test ID number" and was designed to give information to the user as well as link the files (see Figure 1a).




FIGURE 1a. Elements of the Test ID Number.

The first two alphas are an abbreviation of a weapon name, the second two refer to the test stimulus, the numerics provide the link between the three files, and the last alpha indicates whether the test item was an all-up round (A), a rocket motor (P), a warhead (W), or a subcomponent, such as an igniter, fuze, or booster (C). Tests of cartridge-actuated devices (CAD), aircrew escape propulsion systems (AEPS), or pyrotechnics have no alpha following the link number.

In addition to the test ID number, each reference file has its own document serial number incorporating the month and year of publication and the test stimulus (see Figure 1b). Both numbers are displayed on each screen of test data.




FIGURE 1b. Elements of the Document Serial Number.

Options available to the user include data viewing, printing, and manipulation. A summary program will be available in the future. The summary will generate a tabular synopsis of a weapon's reaction to the various IM tests. From the View Existing Data option on the Main Menu, you can choose to view all test data, including the source data for each test. Also available is the option to examine only the source data. All test records include source data, but not all source data are associated with a particular test. Thus, more source records are available if independent access is chosen.

The procedure in this document provides you with a "step-by-step" approach to access the MSIC data. Examples of the various screens are shown on a shaded background and are identified by a figure number. In the text the names of the screens are shown in italics. Sample printouts are provided for selected options. What you are to do and the computer prompts and messages, as well as practice examples, are provided in tabular form. The required keystrokes appear in bold-face type set in brackets, for example |N|. On some illustrations, a shaded area marks an area of inverse video that will appear on your computer screen.

A letter providing installation methods will be part of the installation package, which will be formally published at a later date. Presently you can obtain a copy of the preliminary installation package from EG&G Washington Analytical Services Center, Inc., Attn: Patty Hardekopf; 1396 Piccard Drive; Rockville, Maryland 20850. The MISC and IMET diskettes re also available from EG&G.

### **DATA DICTIONARY**

The NIMIS program package includes several documents, one of which is the "data dictionary." This dictionary will prove to be beneficial if used in conjunction with this document, the user's guide (NWC TP 7068). The data dictionary contains specific information pertaining to data field lengths, data types, and data descriptions. The following example comprises cartridge-actuated devices (CADs) and aircrew escape propulsion systems (AEPS) data dictionary entries.

Abbreviation	Weapon name	Definition
EI	Electrical items	CADs that are electrically initiated to perform a work function.
ВІ	Ballistic items	CADS that are initiated using ballistic (gus) pressure to perform a work function.
DC	Delay cartridges	CADS that accept an input, burn a specified time, and perform a work function.
ET	Explosive transfer lines	Sealed in lines to transfer a signal form input to output device.
ST	Special CAD items	CADs designed for unique aircraft egress requirements.
US	Underseat rockets	AEPS underseat rocket motors.
RC	Rocket catapults	AEPS self-contained rocket catapults.
LR	Large rocket motors	AEPS including rocket motors containing more than 0.5 lb of propellant.
SR	Small rocket motors	AEPS including rocket motors containing less than 0.5 lb of propellant.

### GETTING STARTED

### WARNING....

Data WILL be lost if a diskette is removed improperly.

Always return to the main menu and select either "Q"

for quit or "C" for change diskette BEFORE you attempt

to remove a diskette.

### PRESS ANY KEY TO CONTINUE .

FIGURE 2. Initial Screen.

When using the IBM PC, the diskette can be removed while the program is running. Observe the WARNING to prevent destruction of data.

	Prompts/Comments	What You Do P	
· · · ·	Prompt: Press any key to continue	1) Open program	
	The Opening Screen will appear.		
	· · · · ·		

### **OPENING SCREEN**

	100000	MOOK	22222222	IIIIIIII	22222222222	
	N m M	M m M	88 8 8 8 8	IiiiI	CcccccC	
	Mm m M	Har and	8 8558555	III i III	ce cccccccc	
	Man Mar M	M mXm M	Ss S	Ii iI	C cC	
	Mm MM mM	Mar Honga M	8 85	IiI	Cc C	
	Man Man M	M mM Mm M	Ss S	Ii iI	C cC	**
	Man M M anM	Man Man M	S sS	I i l	Cc C	
	на мам	Man Man N	SE SSSSSSS	Ii iI	C cC	
	••	Man M man	S = 8 8 8S	III	Cc C	÷
		Man Mar M	SSSSSSS S	Ii iI	C cC	:
•		Mar H as	S as	IiI	Cc C	
	M mM M		5s 5	Ii iI	C cC	
		Mar M	S &S	IiI	Cc C	
	M mM	Man M	8888888 S	IIIi iIII	C cC	
	Mm M	M mM	S = = = =S	IiiiI	Cc C	
	M mM	10000	88888888	IIIIIIII	C cC	
	Mm M			••	Cc C	
	M mM	MINIT	CIONS STATUS		c ecccccccc	
	Mm M		LATION CENTER	ì	CcccccC	
	MANAN		Sep 1989	•	22222222222	
	,	•	D-p 2000			
	WHAT	DRIVE ARE THE	PROGRAM FILE	S IN [A,B,C	or D] ?	

FIGURE 3. Opening Screen.

This screen continues to appear as you answer the computer prompts.

No [N] should be entered in response to the third prompt on the first program boot for the day. (The system will update the files.) If you are working with diskettes, [N] must be entered each time you exit the program and use a different diskette. The yes [Y] response is simply a timesaver when you are sure the index files are updated and correct. The Main Menu (Figure 4) screen will appear after either.

Practice Example	Prompts/Comments
1) Open program	Prompt: What drive are the Program files in (A,B,C or D)?
2) Type: A, B, C or D	Prompt: What drive are the Data files in (A,B,C or D)?
3) Type: A, B, C or D	Prompt: Are the files currently indexed on Drive (Y/N) ?
4) Type: <b>N</b>	The Main Menu will appear.

### SELECTION OF PROGRAM OPTIONS

Each section in this document will guide you as you choose the various options and menus. The *Main Menu* screen (Figure 4) shows the options that can be selected. The [A] Add New Data and [E] Edit Existing Data options are not available for general use; these options are for users responsible for data gathering.

Most of the following options are available to you:

- |V| View Existing Data lets you view data by test.
- [C] Change Diskettes permits the changing of diskettes as desired.
- (P) Print Data lets you print data by file or by test.
- [5] Run Summary of Data permits a summary of programs by munition.
- [L] List or Locate shows a test by user-specified conditions.
- [M] Select Munitions shows the munition from which you search for data.
- [Q] Quit Program lets you quit the program.

NOTE: Options [C], [S], and [M] are not currently available for the Macintosh version of this program. You will be able to obtain options [S] and [M] at a later date.

Options [5] and [M] are not available for the IBM and IBM compatible version of this program at this time; they will be made available at a later date.

The remainder of this document is devoted to explaining each option. Also, there are practice examples for you to follow so that you become familiar with the organization of the data and the various options provided in this program.

### [V] - VIEW EXISTING DATA




FIGURE 4. Main Menu Screen.

From the Main Menu, shown in Figure 4, if you select the View Existing Data option [V], the Selection of Data screen (Figure 5) will appear. Selecting [1] Source Information allows you to move among the document records, but the test data are not accessible at the same time. The first of a series of screens is identified as Screen 1 of 1 (Figure 5); there will no test ID number referenced at the top of the screen. (The detailed steps for this procedure, as well as further discussion, are provided in the following section.)

NOTE: At some point, you may enter [E] to exit, which will return the system to the Main Menu.

Practice Example	Prompts/Comments	
I) Type: V	Prompt: Please make a selection (V,P,S,L,C OR Q) ?	
	The Selection of Data screen will appear.	

### Do vou want to VIEW data on :

- [1] Source Information
- [2] All Test Data

Please make a selection from the above : Enter a [0] to Return to Main Menu -> 80

FIGURE 5. Selection of Data Screen.

Selection of Data. This menu is generated when you select either [A] Add New Data, [E] Edit Existing Data, or [V] View Existing Data options from the Main Menu. It asks what data you want to work with:

- [1]— Source Information refers to data on the reference documents, which is separated from test information because documents may be entered into the system without having related test records. To access these unrelated document records, the source information must be accessed independently from the test data.
- [2] All Test Data allows you to access the test data as well as the related document data.

Practice Example	Prompts/Comments
1) Type: 2	Prompt: Please make a selection from the above. Enter a [0] to return to the Main Menu => 0
	The Test Screen 1 of 4 will appear.

**NOTE**: A zero will always appear in the field that follows the prompt: "Enter a [0] to return to the Main Menu -> 0." To exit, type [00] or type [0] and press < RETURN > key.

### Accessing Data Files

General test information is arranged and displayed on the first two screens. From the Test Screen 1 of 4 screen you can move through the files by entering responses to program prompts displayed at the bottom of the screen. The message at the top of the screen makes it possible for you to always know exactly where you are in the program. The identifiers at the top of the screen will remain the same as you answer the prompts at the bottom of the screen (Figures 6a, 6b, and 6c). These illustrations show typical screens using pseudo data.

Review Status: PL Test Screen 1 of 4 Test 1 of 5 Update : Doc serial: 6701700 Test\_id Number: 48BI-01W Munition Nomen: Munition Name: 4.85" NEAR Munition Type: ROCKET Munition Mod: Data Classification: U Stimulus: BULLET IMPACT Test Number: TM-121 Test or Analysis ?: TEST Test Date: 01/01/66 Procedure: WR-50 Standard Test?: Baseline Test:Y Procedure : A STANDARD .20 CAL MOMINCEMDIARY BALL PROJECTILE WAS FIRED AT THE WARHEAD. THE DISTANCE FROM WEAPON TO TARGET WAS 500 YDS. Do you want to change [T]est, change [S]oreen on, or [P]rint this test ? Enter a selection [T,S,P or E to Exit] please ..

FIGURE 6a. Test Screen 1 of 4 Screens.

If you select [P] Print This Test from this screen, the complete data sheet will be printed. The printing option is discussed and an example of a complete data sheet is shown beginning on page 29.

### [T] - Change Test

	Practice Example	Prompts/Comments
1)	Notice the identifiers at the top of the screen that tell which screen is dis- played, how many tests in the file, and which one is now displayed	Message: Test Screen 1 of 4 Test 1 of 5
2)	Type: T  Notice that Test Screen 1 of 4 remains the same as your selections are	Prompt: Do you want to change [T]est, change [S]creen on or [P]rint this test? Enter a selection (T.S.P or E to exit) please
	guided via the prompts at the bottom of the screen.	

Review Status: FL Test Screen 1 of 4 Test 1 of 5 Update: / / Doc\_semial: 6701700 Test\_id Number: 48BI-01W Munition Momen: Munition Name: 4.85" NEAR Munition Type: ROCKET Munition Mod: Data Classification: U Stimulus: BULLET IMPACT Test Number: TH-121
Test or Analysis ?: TEST Test Date: 01/01/66 Procedure: WR-50 Baseline Test:Y Standard Test?: Procedure:
A STANDARD .20 CAL MONINCEMDIARY BALL PROJECTILE WAS FIRED AT THE
WARHEAD. THE DISTANCE FROM WEAPON TO TARGET WAS 500 YDS. Do you want to change [T]est, change [S]creen on, or [P]rint this test 7 Enter a selection [T,S,P or B to Exit] please.. The second se

FIGURE 6b. Test Screen 1 of 4 Screens.

### [L] - Locate a Test

The Locate option |L| helps you find a particular file. To use the |L| Locate option, you must know at least some of the test |I|) you want to access (as little as the weapon name abbreviation will suffice). As you become familiar with this system and the data, the Locate function will become more useful.

There is an area of inverse video (shaded) at the bottom of the screen for you to enter the desired field content. Figure 6c shows that fast cookoff for BRAG (another pseudo weapon) [BRFC-] has been entered.

The following abbreviations are used for the various stimuli.

FC - fast cookoff

SC - slow cookoff

BI - bullet impact

FI - fragment impact

SD - sympathetic detonation

Review Status: FL Test Screen 1 of 4 Test 1 of 5 Update: / / Doc serial: 6701700 Test\_id Number: 48BI-01W Munition Momen: Munition Name: 4.85" MEAR Munition Type: ROCKET Munition Mod: Data Classification: U Stimulus: BULLET IMPACT Test Mumber: TM-121 Test or Analysis ?: TEST Test Date: 01/01/66 Procedure: WR-50 Standard Test?: Procedure : A STANDARD .20 CAL MOMINCEMDIARY BALL PROJECTILE WAS FIRED AT THE WARHEAD. THE DISTANCE FROM WEAPON TO TARGET WAS 500 YDS. Enter the test\_id of the record you want to locate-xBMFC-

FIGURE 6c. Partial Test ID Number Used to Locate Test.

NOTE: When you select the Locate option, the test ID number you are presently viewing will appear in the area of inverse video. It will be replaced as you type in the desired (new) test ID number.

Practice Example	Prompts/Comments
1) Type: L	Prompt: Change screen [F]orward, [B]ackward, [L]ocate a test or [E]xit ? Enter a selection (F,B,L or E to exit) please
2) Type: PEBI-01W	Message: Enter the test_id of the record you want to locate->

Although the illustrations in Figures 6a through 6c show pseudo data, for this practice example you access actual test data for Penguin by entering [PE] to locate the first occurrence of Penguin in the file, [BI] to locate the first occurrence of a Penguin bullet impact test, and [-01W] to locate that specific test [PEBI-01W]. (NOTE: Unless you know that the specific test is in the file, do not enter a complete test II) number.)

When you have located the file, you have the option to change the test [T], change the screen on this test [S], or print this test [P].

### (S) - Change Screen

	Practice Example	Prompts/Comments
1)	Notice the identifiers at the top of the screen that tell which screen is displayed, how many tests in the file, and which one is now displayed	Message: Test Screen 1 of 4 Test 1 of 3
2)	Type: \$	Prompt: Do you want to change {T]est, change {S]creen on or {P}rint this test? Enter a selection (T,S,P or E to exit) please
3)	Type: F	Prompt: Change screen [F]orward, [B]ackward or [E]xit? Enter a selection (F,B or E to exit) please
		The Test Screen 2 of 4 will appear.

### General Test Information, Screen 2

Test I) Number: BRFC-01A Doc\_serial: \$504700 Test Screen 2 of 4
Hardware Configuration: Test 1 of 3
THE TEST ITEM WAS AN AUR WITH A TIVE UNIT INSTALLED.

CORMENTS OF RATIONALS:

THE MISSILE TIVE SHAPED CHARGE DETONATED AT :56 AFTER IGNITION.
03:00 AFTER THE TIVE FUNCTIONED, THE NOSE COME WAS EJECTED AND FOUND
21DEG PROM THE A-FRAME. THE TIP OF THE COME WAS ANOTHER 60DEG AWAY.
A 14" X 16" PIECE OF MELTED ALUMINUM BENEATH THE SAF WAS REMOVED.
THE WARHEAD HAD VENTED AND BURNED.

Hazardous Frags: OHEB Consesus: P Number of Components: 5

Do you want to change [T]est, change [S]creen on, or [P]rint this test ? 

Enter a selection [T,S,P or E to Exit] please..

FIGURE 7. Test Screen 2 of 4 Screens.

	Practice Example	Prompts/Comments
1)	Notice identifiers at the top of the screen that tell you which screen is displayed, how many tests in the file, and which one is now displayed	Message: Test Screen 2 of 4 Test 1 of 3
2)	Type: S	Prompt: Do you want to change [T]est, change [S]creen on or [P]rint this test? Enter a selection (T,S,P or E to exit) please
3)	Type: F	Prompt: Change screen [F]orward, [B]ackward or [E]xit? Enter a selection (F,B or E to exit) please
		The Test Screen 3 of 4 will appear.

### Component Data, Screen 3

### Test Screen 3 of 4 Component Data

DOC\_SERIAL: 8504700 TEST\_ID NUMBER: BRFC-01A

PART NOMENCLATURE: PART TYPE: PART MAKE: TIVE

\*\*\*Part name must have data entered to accept component. EMERGETIC LOAD: BLC & ALUN OXIDE

QUANTITY (WEIGHT): .015 LBS

METRIC WEIGHT: 0.0068 KG PART REACTION: DETONATION TIME TO REACTION: 00:10:56

TOP DRAWING NUMBER: SPEC NUMBER:

Component 1 of 5

Do you want to change [C]omponent or change [S]oreen on this test Enter a selection [C,8 or E to Exit] please..

FIGURE 8. Test Screen 3 of 4 Screens.

This screen shows a single component from the test and gives a little detail. There may be several components in a test (i.e., warhead, booster, rocket motor), thus this screen may be repeated several times to display all of the components for one test.

WI	hat You Do	Prompts/Comments
1)	Notice screen identifier located in the top center of the screen that tells you which screen is displayed and the screen title	Message: Test Screen 3 of 4 Component Data
2)	Notice the display near the bottom of the screen that tells you how many components there are and which one is currently displayed	Message: Component 1 of 3

Pr	actice Example	Prompts/Comments
1) Ty	/pe: \$	Prompt: Do you want to change [C]omponent or change [S]creen on this test? Enter a selection (C,S or E to exit) please
2) T <sub>3</sub>	/pe: F	Prompt: Change screen [F]orward, [B]ackward or [E]xit? Enter a selection (F,B or E to exit) please
		The Test Screen 4 of 4 will appear.

Test Data Reference for Test ID Number, Screen 4

Screen 4 of 4
Test Data Reference for Test\_id number BRFC-01A
Document Classification : U

Doc Title : BRAG AIR VEHICLE DEVELOPMENT TEST PROPULSION AND ORDNANCE SAFETY TEST REPORT.

Report No.: MAVAIR 32050-351 NA Report Date : 04/01/85 Report Status : FINAL IMET (Y/N):

Point of Contact (Mane, Agency , Phone)
WILL BOX, MAVAIR, AUTO PARK, CA, 619-371-2830

Dogument Serial Number : 8504700

From here, you may change screens [B]ackward to the component data, or you may change screens [F]orward to the first screen of this test.

Please enter your selection [F,B or E to Exit] [7]

FIGURF 9. Screen 4 of 4 Screens.

You are now on the final screen of data for a single test. The screen in Figure 9 shows source information for the test. You may not change tests from this screen, nor can you change to another document. You can only change screens forward to Test Screen 1 of 4 (the first screen of general test information) or backward to Test Screen 3 of 4, Component Data.

	Practice Example	Prompts/Comments
1)	Notice screen identifier located in the top center of the screen that tells which screen is being displayed and its title	Message: Screen 4 of 4 Test Data Reference for Test_id number
2)	Type: E	Prompt: From here you may change screen [B]ackward to the component data or you may change screens [F]orward to the first screen of this test. Please enter your selection (F,B or E to exit) ?
		The Main Menu screen will appear.

### [C] — CHANGE DISKETTE




FIGURE 10a. Main Menu Screen.

From the Main Menu, when you select the [C] Change Diskette option, the screens shown in Figure 10b then Figure 10c will appear to guide you. When you are finished, the system will return to the Main Menu.




FIGURE 10b. Change Diskette Instructions.

Is this data diskette currently indexed on drive B: [Y/N]?

FIGURE 10c. Instructions Continued.

Practice Example	Prompts/Comments
1) Type: N	Prompt: Is this data diskette currently indexed on drive D: [Y/N]?
	The system returns to Main Menu.

### [P] - PRINT DATA




FIGURE 11. Main Menu Screen.

You have now returned to the *Main Menu* screen. Since you know that [A], [E], and [V] work in the same manner, now try the Print Data [P] function. Two types of printout are available with this option:

- [1]— Print Test Data will print out all of the data in the three data groups on each test in an orderly and arranged manner.
- [2] Print Component Data prints out the component data of a test.
- [3] Exit Without Printing returns the system to the Main Menu screen.

Selection of either [1] or [2] generates the Print Options screen.

The Print Data prompt (Figure 12) will appear when you follow the Practice Example.

Practice Example	Prompts/Comments
1) Type: <b>P</b>	Prompt: Please enter selection (A.E.,V.P.L.C.M or Q) ?
	The Print Data prompt will appear.




FIGURE 12. Print Data Prompt on Main Menu.

Setting Filter Conditions. Setting filter conditions allows you to choose one to five fields to specify desired printout result. The procedure is given in the Practice Examples.

To continue without setting filter conditions, respond [N] to the prompt displayed on the screen. The *Print Data* screen (Figure 14a) will appear, and you will follow the procedure beginning on page 29. All test records on floppy disk will be printed. If your data are on the hard disk, every record for every weapon will be printed.

Practice Example	Prompts/Comments
1) Type: Y	Prompt: Do you wish to set a filter condition before printing [Y/N] ?
	The Set Filter screen will appear.

Figure 13a shows a sampling of various filter conditions. The illustration shows that [18] has been selected. Notice that the area of inverse video changes as you make entries (Figures 13b and 13c) following the Practice Examples.

# COMMAND -> SET FILT [01] TEST ID MUMBER [02] DOC SERIAL MUMBER [03] PART MOMENCLATURE [04] PART MOMENCLATURE [05] PART HOME (WARMERD, FUSE, ETC.) [05] PART TYPE (WARMERD, FUSE, ETC.) [05] PART TYPE (ADAPTER, IMERT, ETC.) [06] EXPLOSIVE LOAD [07] EXPLOSIVE LOAD [08] COMPONENT REACTION [08] COMPONENT REACTION [09] TIME TO REACTION [10] METRIC WEIGHT [11] TOP DRAWING MUMBER [12] SPEC MUMBER [12] SPEC MUMBER [13] MUHITION MANE [24] RATIONAL/COMMENT [15] SPEC MUMBER [25] BASELIME TEST [16] STAMDARD TEST [17] MUHITION MANE [27] IMET DOCUMENT ENTER FROM 1 TO S FIELDS TO WHICH YOU WISE TO SET CONDITIONS FOR YOUR COMMAND. ENTER A [0] TO SELECT A SEARCH RANGE.

FIGURE 13a. Set Filter Screen.

Practice Example	Prompts/Comments
1) Type: <b>18</b>	Prompt: Enter from 1 to 5 fields which you wish to set conditions for your command. Enter a [0] to end your selections.
	Message: Test Date
2) Type: =	Prompt: Enter [<], [<=], [>], [>=], [=], or [#] to select a search range.
3) Press < RETURN >	Message: Test Date =

```
Command -> SET FILT

[01] TEST ID NUMBER
[02] DOC SERIAL MUMBER
[03] PART MOMENCLATURE
[04] PART MOMENCLATURE
[04] PART MAME (WARKEAD, FUSE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
[06] EXPLOSIVE LOAD
[07] EXPLOSIVE LOAD
[08] COMPOMENT REACTION
[08] COMPOMENT REACTION
[09] TIME TO REACTION
[10] METRIC WEIGHT
[11] TOP DRAWING MUMBER
[22] PROCEDURE
[12] SPEC MUMBER
[24] RATIONAL/COMMENT
[15] MUNITION MAME
[25] BASELINE TEST
[12] SPEC MUMBER
[26] STAMDARD TEST
[17] MUNITION MAME
[27] IMET DOCUMENT

ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET COMDITIONS
FOR YOUR COMMAND. ENTER A [0] TO SELECT A SEARCH RANGE.
```

FIGURE 13b. Prompt to Set Condition, Test Date.

Practice Example	Prompts/Comments	
1) Type: <b>01/01/90</b>	Message: Test Date = 01/01/90	
2) Type: Y	Prompt: Are you satisfied with the above condition $[Y/N]$ ?	
3) Type: <b>Y</b>	Prompt: Are you ready to execute the command $[Y/N]$ ?	
4) Type: <b>00</b>	The Print Data screen will appear.	

### Seeth devine beiseen viist een en en een de seet en seel en de seed en bestel en de de een een de begege Command -> SET FILT [01] TEST ID NUMBER [14] MUNITION NOMENCLATURE [02] DOC\_SERIAL NUMBER [15] MUNITION MODIFICATION [03] PART HOMENCLATURE [16] NSM MUMBER [17] NALC MUMBER [04] PART NAME (WARHEAD, FUSE, ETC.) [05] PART TYPE (ADAPTER, INERT, ETC.) [19] DATA TYPE (TEST OR AMALYSYS) [06] EXPLOSIVE LOAD TEST STIMULUS [20] [07] EXPLOSIVE LOAD WEIGHT [21] TEST DATE [08] COMPONENT REACTION [22] PROCEDURE [09] TIME TO REACTION [23] EAZARDOUS PRAGMENTS [10] METRIC WEIGHT [24] RATIONAL/CONNENT [11] TOP DRAWING MUMBER [25] BASELIME TEST [26] STANDARD TEST [12] SPEC NUMBER [13] NUMITION MAKE [27] IMBT DOCUMENT ENTER FROM 1 TO 5 FIELDS TO WEICH YOU WISE TO SET CONDITIONS FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 21 TEST DATE = 01/01/90 EMTER [<],[<=],[>],[>=],[=] or [#] TO SELECT A SEARCE RANGE.

### FIGURE 13c. Selection of Test Cata.

```
Command -> SET FILT
       [01] TEST ID NUMBER
                                                    [14] MUNITION MONENCLATURE
[15] MUNITION MODIFICATION
       [02] DOC SERIAL MUMBER
       [01] PART NOMENCLATURE
                                                     [16] MSN MUNDER
       [04] PART NAME (WARREAD, PUBE, ETC.)
                                                     [17] MALC MUMBER
       [05] PART TYPE (ADAPTER, INERT, ETC.)
                                                     [19] DATA TYPE (TEST OR AMALYSIS)
[20] TEST STIMULUS
      [04] EXPLOSIVE LOAD
[07] EXPLOSIVE LOAD WEIGHT
                                                     [20]
                                                          TEST DATE
                                                     [21]
      [08] COMPONENT REACTION
[09] TIME TO REACTION
                                                     [22] PROCEDURE
                                                     [23]
                                                          EXEXADOUS
                                                                      PRAGMENTS
       [10] METRIC WEIGHT
                                                     [24] RATIONAL/CONNENT
       [11] TOP DRAWING NUMBER
[12] SPEC NUMBER
                                                     [25] BASELIME TEST
[26] STANDARD TEST
                                                     [26]
       [13] NUMITION MAKE
                                                     [27] INST DOCUMENT
          ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET CONDITIONS
          FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 21
                 ARE YOU SATISFIED WITH THE ABOVE CONDITION (Y/N) 1070
           A REPLY OF (Y) ES WILL ADD THE ABOVE CONDITION TO THE COMMAND.
```

FIGURE 13d. Final Prompt to Select of Test Date.

When you have completed the procedure for setting filter conditions, the *Print Data* screen (Figure 14a) will appear.

### [1] - Print Test Data

	רו רוורוור			רר רדרררו	
A section of the sect	)] [1]	PRINT TEST	DATA	11 11	
	אָל הַ י	PRINT COMP		7.7	
	٦٦ - ٠	LILL WITHO		۲۲ - ۳۳	
	PLEASE ENTER				

FIGURE 14a. Print Data Screen.

The Practice Example in this section describes the steps for executing the [1] Print Test Data option.

Printing Options. The data gathered and input for the MSIC system are contained on diskettes and grouped by munition. You have two options for printing or you can exit this menu:

- [1] Print Entire File allows you to print all of the data for a specific munition.\*
- [2] Select Records for Print lets you select specific tests for printing. Selection of this option generates a screen displaying all of the test ID numbers of the tests in the data files; you may view all of the test ID numbers available, then enter as many test IDs as you desire.
- [3] Exit Print Option lets you leave the Print Options screen. The system returns to the Main Menu screen.

Practice Example	Prompts/Comments	
1) Type: 1	Prompt: Please enter your selection (1,2 or 3).	
	The Print Options screen will appear.	

<sup>\*</sup> CAUTION: Selecting [1] prints the entire file. Be aware of the number of records because there is no way to interrupt the printing function.

PRINT OPTIONS 111111111111111111111111111111111111
11
33 [2] SELECT RECORDS TO PRINT 33 33 33 [3] EXIT PRINT OPTION 33
33 33333333333333333333333333333333333
Please enter your selection ?

FIGURE 14b. Print Options Screen.

Practice Example	sample Prompts/Comments	
1) Type: 2	Prompt: Please enter your selection ?	
	The Available Test_id for Printing screen will appear.	

Figure 15a shows a sample screen of test ID numbers available for printing. Each screen can contain up to 30 test ID numbers. The system will generate as many screens as needed until you have viewed all of the test ID numbers desired and you end the selection process.

1 BRFC-03A 2 BSFI-01P 3 HNSD-01P
4 NRBI-01W 5 RESC-01W 6 RMFC-01P
7 WFBI-01C

There are 1 screen(s) of 30 records max each that may be selectively printed. Enter the number adjacent to the test\_id you wish to print. Enter [0] to end selections.->

FIGURE 15a. Sample Screen of Available Test IDs for Printing.

	Practice Example	Prompts/Comments
1)	Type: 01 You may enter as many numbers as there are available. You must enter 0 before a 1-digit number.	Prompt: Enter the number adjacent to the test_id you wish to select. Reenter the adjacent number for tests you wish to de-select. Enter [0] to end selections> 0
2)	Notice your selections will be highlighted as you enter the two-digit identifier.	
3)	Type: <b>00</b>	When printing is completed, the system returns to the Main Menu.

A presout of test data for a pseudo weapon is shown in Figure 15b. When printing is completed, the system returns to the Main Menu.

DATE : 08/24/90

PRELIMINARY

OHER Consensus : PASS

Review Status : F

**Munition Identification** 

Document Serial Number : 8504700

MISSILE : BRAG MK 82

Test ID Number : BRFC-03A

Munition Modification:

NSN Number:

NALC Number:

Quantity

Test Item Components

<u>Material</u>

Netric

Energetic

......TIVS

BLC & ALUM OXIDE .015 LBS

0.0068 KG

### <u>Summary Test Results</u>

Test Date : 04/26/84

Video Project Number:

Stimulus : FAST COOKOFF TEST

Baseline Tost: Y

Standard Test: N

Time To

Conclusion(s):

TIVE : DETONATION

Reaction 00:10:56

Config : THE TEST ITEM WAS AN AUR WITH A TIVE UNIT INSTALLED.

Procedure : MIL-STD-1648A(AS)

THE TIME TO 1000 F FLAME TEMP WAS :40 SEC.

Comments : THE MISSILE TIVE SHAPE CHARGE DETONATED AT :56 AFTER IGNITION. 03:00 AFTER THE TIVE FUNCTIONED, THE MOSE COME WAS EJECTED AND FOUND

17 FT FROM THE A-FRAME. TIP OF THE CONE WAS 30 FT AWAY FROM THE PIT A 14" X 16" PIECE OF MELTED ALUMINUM BENEATH THE ITEM WAS REMOVED.

WARHEAD VENTED AND BURNED.

Hazardous Frags : N

### Source Information

Title:

BRAG AIR VEHICLE DEVELPONENT TEST PROPLUSION AND ORDNANCE SAFETY

TEST REPORT

Report Number

: NAVAIR 32050-351 NA

Document Classification : UNCLASSIFIED

Test Number Report Date : SEC 12-11 A

Date Type

: 04/01/85

Report Status

: TEST : FINAL

Point Of Contact

WILL BOX, MAVAIR, AUTO PARK, CA. 619-371-2830

FIGURE 15b. Sample Printout of Test Data for Pseudo Weapon.

This concludes operation of the [1] Print Test Data option.

### [2] - Print Component Data

You have now returned to the Main Menu screen (Figure 16).

	######################################	WISK TO	
	(V) VIEW EXISTING DATA		
	(C) CHANGE DISKETTES	(S) RUN SUMMARY PROGRAM	
	(L) LIST OR LOCATE	(Q) QUIT PROGRAN	
 6, 1 1, 1 1, 1			
	Do you wish to set a filter	condition before printing [Y/N]	

FIGURE 16. Main Menu Screen.

Again working from the Print Data [P] menu (Figure 17), the Practice Example in this section describes the steps for executing the [2] Printing Component Data option.

Practice Example	Example Prompts/Comments	
1) Type: <b>P</b>	Prompt: Please enter selection (V,P,S,L,C or Q) ?	
2) Type: <b>N</b>	Prompt: Do you wish to set a condition before printing [Y/N]?	
	The Print Data screen will appear.	

If you want to set conditions before printing, respond (Y); you will follow the steps beginning on page 42, "Setting Conditions for List."

```
DEFASE ENTER AOMS SEFECTION [ 1'5 OK 3 ]
```

FIGURE 17. Print Data Screen.

Following the steps in the Practice Example, the *Print Options* screen (Figure 18) will appear. When you select [3] Exit Without Printing, the system returns to the *Main Me..u* screen.

Practice Example	Prompts/Comments
1) Type: 2	Prompt: Please enter your selection (1,2 or 3).
	The Print Options screen will appear.

PRINT OPTIONS
111111111111111111111111111111111111111
11 11 [1] PRINT ENTIRE FILE 33 33 33 33
33 [2] SELECT RECORDS TO PRINT 33 33
33 [3] EXIT PRINT OPTION 33 33
33333333333333333333333333333333
Please enter your selection ?

FIGURE 18. Print Options Screen.

Printing Options. Definitions of the print options displayed on the Print Options screen are repeated here for convenience.

- [1] Print Entire File allows you to print all of the data for a specific munition.\*
- [2] Select Records for Print lets you select specific tests for printing. Selection of this option generates a screen displaying all of the test ID numbers of the tests in the data files; you may view all of the test ID numbers available, then enter as many test IDs as you desire.
- [3] Exit Print Option lets you leave the Print Options screen. The system returns to the Main Menu screen.

Practice Example	Prompts/Comments
1) Type: 2	Prompt: Please enter your selection ?
	The Available Test_id for Printing screen will appear.

Figure 19 shows a sample screen of test ID numbers available for printing. Each screen can contain up to 30 test ID numbers. The system will generate as many screens as needed until you have viewed all of the test ID numbers desired and you end the selection process by entering [00].




FIGURE 19. Sample Screen of Available Test IDs for Printing.

<sup>\*</sup> CAUTION: Selecting [1] prints the entire file. Be aware of the number of records because there is no way to interrupt the printing function.

	Practice Example	Prompts/Comments
1)	Type: 01	Prompt: Enter the number adjacent to
2)	Press < RETURN >	the test_id you wish to select. Re- enter the adjacent number for tests you
3)	Type: <b>02</b>	wish to de-select. Enter [0] to end selections> 0
4)	Press < RETURN >	serections> 0
5)	Type: <b>03</b>	
6)	Press < RETURN > You may enter as many numbers as there are available. You must enter 0 before a 1-digit number.	
7)	Notice your selections will be highlighted as you enter the two-digit identifier.	
8)	Туре: 00	When printing is completed, the system returns to the Main Menu.

The examples shown in Figure 20, although for pseudo weapons, are typical of component data printouts. When printing is completed, the system returns to the Main Menu.

DATE: 08/24/90

MUNITION NAME : HARDNOSE MK 99 TEST ID NUMBER: HNSD-01P

ENERGETIC MATERIAL			
COMPONENT NAMES	QUANTITY	SPEC NO.	TOP DRAWING NO
***************	*************	**********	*********
MK 99	REDFRO 20		
ROCKET MOTOR DONOR	8C LBS		
MK 99	REDFRO 20		
ROCKET MOTOR ACCEPTOR	80 LBS		
	4-1		

(a) FIGURE 20. Sample Printouts of Component Data.

DATE: 08/24/90

NUNITION NAME : BRAG MK 82 TEST ID NUMBER: BRFC-03A

ENERGETIC MATERIAL

COMPONENT NAMES QUANTITY SPEC NO. TOP DRAWING NO

BLC & ALUM OXIDE

TIVS .015 LBS

(b)

DATE: 08/24/90

MUNITION NAME : BLUE STAR MK 13

TEST ID NUMBER: BSFI-01P

ENERGETIC MATERIAL

COMPONENT NAMES QUANTITY SPEC NO. TOP DRAWING NO

MK 13

HARDEX

ROCKET MOTOR

82 LBS

(c)

FIGURE 20. (Contd.)

This concludes operation of the [2] Print Component Data option.

[S] — RUN SUMMARY PROGRAM. This option is not for general use and is not disussed in this document.

## [L] - LIST OR LOCATE




FIGURE 21. Main Menu Screen.

The [L] List or Locate option allows you to find, list, or look at test data that meet certain user-defined conditions. As you become more familiar with the system and the data, this function becomes more useful.

Practice Example	Prompts/Comments
1) Type: <b>L</b>	Prompt: Please enter a selection (V,P,S,L,C or Q).
	The List or Locate screen will appear.

#### [1] — List to Screen and [2]—List to Printer




FIGURE 22. List or Locate Screen.

The options for [1] List to Screen and [2] List to Printer do the same thing, but the list is printed when [2] is selected. Choosing either list option ([1] or [2]) lets you list (select) the contents of one to five data sheets (fields).

Practice Example	Prompts/Comments	
1) Type: 1	Prompt: Enter your selection (1,2,3 or 4)	
	The Field Selection screen will appear.	

Following the Practice Example, the next section shows you how to use the [1] List to Screen option. When either [1] or [2] is selected, searching is done through the Component file; therefore, if more than one component of a single test is found that meets all conditions set, the same test ID number will be displayed for each occurrence.

```
TEST ID MUMBER
                                           MUNITION MOMENCLATURE
    DOC SERIAL NUMBER
                                           NUMITION MODIFICATION
1021
                                       [15]
    PART MOMENCUATURE
                                       [16]
                                            MSM MOMBER
    PART MAME
               (WARHEAD, FUSE, ETC.)
                                           MALC NUMBER
               (ADAPTER, IMERT, ETC.)
                                           DATA TYPE (TEST OR AMALYSIS
    EXPLOSIVE LOAD
                                            TEST STIMULUS
    EXPLOSIVE LOAD WEIGHT
                                            TEST DATE
                                            PROCEDURE
    COMPONENT REACTION
                                                        PRAGNENTS
                                            RAZARDOUS
    TIME TO REACTION
    METRIC WEIGHT
                                            RATIONAL/COMMENT
    TOP DRAWING MUMBER
                                            BASELINE TEST
    SPEC MUMBER
                                           STANDARD TEST
    NUNITION MAKE
                                       [27] IMBT DOCUMENT
  ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET COMDITIONS
  FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS.
```

FIGURE 23a. Field Selection Screen for List Option.

Field Selections for List Option. For both List to Screen [1] and List to Printer [2] options you may view the contents of up to five data fields. It is recommended that you select the test ID number [01] as one of fields so that if more information on the listed data is needed, the file can be accessed by the test ID number. The system automatically ends the selection process when you have selected five fields. If you choose less than five fields, you must enter [00] to tell the system that you have completed the selection procedure.

Practice Example	Prompts/Comments
1) Type: 01,08, and 23	Prompt: You may select from 1 to 5 fields to list out from those listed
2) Type: <b>00</b>	above. Enter a [0] to end your selections. O
	The List screen will appear.

The Command line will build (Figures 23b, 23c, and 23d) until you have entered five selections or you end the selection process by entering [00] or [0] < RETURN >.

```
Command -> LIST Test_id
                                                         [17] MALC NUMBER
[18] DATA CLASSIFICATION
[19] DATA TYPE (TEST OR AMALYSIS)
       [01] TEST ID NÜMBER
        [02] DOC_SERIAL MUMBER
[03] PART MOMEMCLATURE
        [04] PART MAME (WARHEAD, FUSE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
                                                         [20] TEST STIMULUS
[21] TEST DATE
        [06] EXPLOSIVE LOAD
                                                         [22] PROCEDURE
        [07] EXPLOSIVE LOAD WEIGHT
[08] COMPONENT REACTION
                                                         [23] HARARDOUS FRAGMENTS
                                                         [24] RATIONAL/COMMENT
        [09] TIME TO REACTION
[10] METRIC WEIGHT
                                                         [25] BASELINE TEST
                                                         [26] STANDARD TEST
[27] INST DOCUMENT
        [11] TOP DRAWING NUMBER
        [12] SPEC NUMBER
                                                         [28] DOCUMENT CLASSIFICATION [29] DOCUMENT TITLE
        [13] HUNITION MAKE
        [14] MUNITION MOMENCLATURE
                                                         [30] DOCUMENT DATE
        [15] MUNITION MODIFICATION
                                                         [31] REPORT NUMBER
        [16] MBM NUNDER
                                                         [32] CONTACT (PGC)
             YOU MAY SELECT PRON 1 TO 5 FIELDS TO LIST OUT FROM THOSE
             LISTED ABOVE. ENTER A (0) TO END YOUR SELECTIONS.
```

FIGURE 23b. Field Selection Screen With One Selection Shown on Command Line.

```
Command -> LIST Test_id, Reaction
       [01] TEST ID NUMBER
                                                      [17] MALC MUMBER
       [02] DOC_SERIAL NUMBER
[03] PART MONEMCLATURE
                                                       [18] DATA CLASSIFICATION
       [03] PART MOMEMCLATURE
[19] DATA TYPE (TEST OR ANALYSIS)
[04] PART MAME (WARHEAD, FUNE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
[06] EXPLOSIVE LOAD
[22] PROCEDURE
       [07] EXPLOSIVE LOAD VRIGHT
                                                       [23] BARARDOUS FRAGMENTS
                                                      [24] RATIONAL/COMMENT
[25] BASELINE TEST
       [08] COMPONENT REACTION
       [09] TIME TO REACTION
       [10] METRIC WEIGHT
                                                      [26] STANDARD TEST
[27] INET DOCUMENT
       [11] TOP DRAWING NUMBER
       [12] SPEC NUMBER
[13] MUNITION MANS
                                                       [28] DOCUMENT CLASSIFICATION
                                                       [29] DOCUMENT TITLE
       [14] MUNITION MONENCLATURE
                                                       [30] DOCUMENT DATE
       [18] MUNITION MODIFICATION
                                                       [21] REPORT MUMBER
       [16] MSM MUMBER
                                                       [31] CONTACT (POC)
            YOU MAY RELECT FROM 1 TO 5 FIELDS TO LIST OUT FROM THOSE
            LISTED ABOVE. ENTER A [0] TO BND YOUR SELECTIONS. 0
```

FIGURE 23c. Field Selection Screen With Two Selections Shown on Command Line.

NOTE: Disregard "B > " on the Command line; it is an internal computer command.

```
Command -> LIST Test_id, Reaction, B->test_date
                                               [17] MALC MUMBER
      [01] TEST ID MUMBER
      [02] DOC_SERIAL MUMBER
                                               [18] DATA CLASSIFICATION
      (03) PART MOMENCLATURE
                                               [19] DATA T.'PE (TEST OR AMALYSIS)
      [04] PART MAME (WARHEAD, FUZE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
                                               [20] TEST STANULUS
                                               [21] TEST DATE
      [06] BIPLOSIVE LOAD
                                               [22] PROCEDURE
      [07] EXPLOSIVE LOAD WEIGHT
                                                [23] HASARDOUS FRAGHENTS
      [08] COMPONENT REACTION
                                                [24] RATIONAL/COMMENT
      [09] TIME TO REACTION
                                                [25] BASELIME TEST
      [10] MRTRIC WEIGHT
                                               [26] STANDARD TEST
                                               [27] INST DOCUMENT
           TOP DRAWING MUMBER
      [12] SPEC NUMBER
                                                [28] DOCUMENT CLASSIFICATION
      [13] NUMITION MAKE
                                                [29] DOCUMENT TITLE
       [14] MUNITION MOMENCLATURE
                                                [30] DOCUMENT DATE
      [15] MUNITION MODIFICATION
                                               [31] REPORT MUNBER
                                               [32] CONTACT (POC)
      [16] NSM NUMBER
          YOU MAY SELECT FROM 1 TO 5 FIELDS TO LIST OUT FROM THOSE
          LISTED ABOVE. ENTER A (0) TO END YOUR SELECTIONS.
```

FIGURE 23d. Field Selection Screen With Three Selections Shown on Command Line.

Setting Conditions for List. When you have finished selecting fields, you may set some conditions for searching the data files. If you respond yes [Y] to the computer prompt, the screen will change as shown in Figure 23c.

```
Command -> LIST Test_id, Reaction, B->test_date
       [OL] TEST ID MUMBER
                                                   [17] MALC MUMBER
                                                   [18] DATA CLASSIFICATION
       [02] DOC_SERIAL NUMBER
       [03] PART MONENCLATURE
                                                   [19] DATA TYPE (TEST OR AMALYSIS)
       [04] PART MAME (WARHEAD, FUSR, ETC.)
[05] PART TYPE (ADAPTER, IMMRT, ETC.)
                                                   [20] TEST STINULUS
                                                   [21] TEST DATE
       [06] EXPLOSIVE LOAD
                                                   [22] PROCEDURE
       [07] EXPLOSIVE LOAD WEIGHT
                                                   [23] HASARDOUS FRAGMENTS
       [08] COMPONENT REACTION
                                                   [24] RATIONAL/COMMENT
       [09] TIME TO REACTION
                                                   [25] BASELINE TEST
       [10] METRIC WEIGHT
                                                   [26] STANDARD TEST
       [11] TOP DRAWING MURBER
                                                        IMET DOCUMENT
                                                   [27]
       [12] SPEC NUMBER
                                                   [28] DOCUMENT CLASSIFICATION
       [13] NUMITION MAKE
                                                   [29] DOCUMENT TITLE
       [14] NUMITION MONENCLATURE
                                                   [30] DOCUMENT DATE
       [15] NUMITION MODIFICATION
                                                   [31] REPORT MUMBER
       (16) NOW NUMBER
                                                   [32] CONTACT (POC)
           YOU MAY SELECT FROM 1 TO 5 FIELDS TO LIST OUT FROM THOSE
           LISTED ABOVE. ENTER A [0] TO END YOUR SELECTIONS.
            Do you want to set some conditions for your list [7/N] @ 10
                    Barrier and the second of the second sec
```

FIGURE 23e. Field Selection Screen With Conditions Prompt.

Practice Example	Prompts/Comments	
1) Type: Y	Prompt: Do you want to set some conditions for the list (Y/N) ?	
	The Condition screen will appear.	

Your response will lead to the Condition screen (Figure 24a) to allow your selection of the desired conditions. The Command line continues to show the selections you have already made, while the conditions available appear in the listing. You are limited to five conditions.




FIGURE 24a. Condition Screen.

	Practice Example	Prompts/Comments
1)	Туре: 20	Prompt: Enter from 1 to 5 fields to which you wish to set conditions for your command. Enter a [0] to end your selections.
2)	Type: Y	Prompt: Would you like to see the list of existing field entries [Y/N] ?
3)	Notice the position of the pointer as you type the appropriate response.	The list appears on the screen.

At this point the computer prompt asks if you want to see a list of what is actually in the file in that field. Follow the Practice Example to select this option. Figure 24b is the list that will be displayed on the computer screen.

If you already know what you want, this list can be by-passed by responding [N].

BULLET IMPACT PRAGMENT IMPACT	BULLET IMPACT TEST SLOW COOKOFF	FAST COOKOFF SYMPATHETIC D	ETONATION -
1.0 M. M.			<u>;</u> ;
			<u>.</u>
te Maria			
			1
			-
			*
:   1:-			
B-	>Stimulus ? FAST COOKOFF		
Enter '=' (e	qual to) or '#'(not equal to)		

FIGURE 24b. Example of List of Stimuli.

Figure 24b shows that Fast Cookoff has been typed; the area of inverse will show your selections as you follow the Practice Example.

Practice Example	Prompts/Comments	
1) Type: Fast Cookoff	Message: B->Stimulus ?	
2) Press < RETURN >	D	
3) Type: =	Prompt: Enter '=' (equal to) or '#' (not equal to)	
4) Press < RETURN >	The Condition screen appears on the screen.	

After entering the stimulus, you return to the Condition screen (Figure 25a). The illustration shows that [17] Test Stimulus was selected, then fast cookoff was typed in. The area of inverse video is indicated. If you answer yes [Y], the condition is added to the Command line. If you answer no [N], the condition is abandoned and the Command line remains the same.

```
Command -> LIST Test_id, Reaction, B->test_date
 FOR B->Stimulus = 'FAST COOKOFF'
                                                   [14] MUNITION MOMENCLATURE
       [01] TEST ID NUMBER
                                                    [15] MUNITION MODIFICATION
       [02] DOC_SERIAL MUMBER
       [03] PART MOMENCLATURE
                                                    (16) MON MUMBER
       [04] PART MAME (WARMERAD, PUBE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
                                                    [17] MALC MUMBER
                                                   (19) DATA TYPE (TEST OR AMALYSIS)
[20] TEST STIMULUS
       [06] EXPLOSIVE LOAD
       [07] EXPLOSIVE LOAD WEIGHT
                                                    [21] TEST DATE
       [08] COMPONENT REACTION
[09] TIME TO REACTION
                                                        PROCEDURE
                                                    [22]
                                                    [23] EASARDOUS FRAGMENTS
                                                    [24] RATIONAL/COMMENT
       [10] METRIC WEIGHT
       [11] TOP DRAWING NUMBER
[12] SPEC NUMBER
                                                    [25] BASELIME TEST
                                                    [26] STANDARD TEST
       [13] NUMITION MAKE
                                                    [27] IMET DOCUMENT
          ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET COMDITIONS
          FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 0
```

#### FIGURE 25a. Condition Screen.

Three of the fields are treated as special cases: Time to Reaction, Test Date, and Component Reaction. You are given the option of using equality or inequality symbols in setting the conditions (<, < =, >, > =, =, or #).

The Condition screen will continue to appear and the area of inverse video will show your selections as you make entries (Figures 25b and 25c).

Practice Example	Prompts/Comments
1) Type: 21	Prompt: Enter from 1 to 5 fields to which you wish to set conditions for your command. Enter a [0] to end your selections.
2) Type: >	Message: Test Date
3) Press < RETURN >	Message: Test Date >
4) Type: 01/01/86	Message: Test Date > 01/01/86
Notice the area of inverse video where the cursor guides your entries.	The Command line changes as conditions are set.

```
Command -> LIST Test id, Reaction, B->test_date
FOR B->Stimulus = 'FAST COCKOFF'
                                                              [14] MUNITION MOMENCLATURE
        [01] TEST ID MUMBER
                                                              [15] MUNITION MODIFICATION
[16] MBN MUNBER
        [02] DOC_SERIAL MUMBER
         [03] PART MOMENCLATURE
        [04] PART NAME (WARREAD, FUSE, ETC.)
[05] PART TYPE (ADAPTER, INERT, ETC.)
[06] EXPLOSIVE LOAD
                                                             [17] BALC NUMBER
[19] DATA TYPE (TEST OR ANALYSIS)
[20] TEST STINULUS
                                                              [21] TEST DATE
[22] PROCEDURE
[23] HASARDOUS PRAGMENTS
         [07] EXPLOSIVE LOAD WEIGHT
         [08] COMPONENT REACTION
         [09] TIME TO REACTION
                                                              [24] RATIONAL/CONMENT
[25] BASELINE TEST
         [10] METRIC WEIGHT
         [11] TOP DRAWING NUMBER
                                                              [26] STANDARD TEST
[27] INST DOCUMENT
         [12] SPEC NUMBER
         (13) NUNITION NAME
            ENTER FROM 1 TO 5 FIELDS TO WEICH YOU WISH TO SET CONDITIONS
FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 21
                      TEST DATE
       ENTER [<], (<=), [>], [>=], [=] or [#] TO SELECT A SEARCH RANGE.
```

FIGURE 25b. Condition Screen With One Condition Selected.

```
Command -> LIST Test_id,Reaction,8->test_date
FOR 8->Stimulus = 'YAST COORDY?'
                                                             [14] MUNITION MOMENCLATURE
        [01] TEST ID NUMBER
                                                             [15] MUNITION MODIFICATION
        [02] DOC SERIAL NUMBER
[03] PART NOMENCLATURE
                                                             (16) MEN NUMBER
        [04] PART MAME (WARREAD, FUSE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
[06] EXPLOSIVE LOAD
[07] EXPLOSIVE LOAD WEIGHT
[08] COMPONENT REACTION
                                                            [17] MALC NUMBER
[19] DATA TYPE (TEST OR AMALYSIS)
[20] TEST STIMULUS
                                                             [21] TEST DATE
[22] PROCEDURE
         [09] TIME TO REACTION
                                                             [23] HABARDOUS FRAGHENTS
         [10] METRIC WEIGHT
                                                             [24] RATIONAL/CONCENT
         [11] TOP DRAWING MUMBER
                                                             [25] BASELINE TEST
                                                             [26] STANDARD TEST
[27] IMET DOCUMENT
         12) SPEC NUMBER
         [13] MUNITION NAME
            EMTER FROM 1 TO 5 FIELDS TO WEICH YOU WISH TO SET COMDITIONS
            FOR YOUR COMMAND. EMTER A [0] TO END YOUR SELECTIONS. 21
                      TEST DATE > 01/01/86
       ENTER [<],[<=],[>],[>=],[=] or [#] TO SELECT A SEARCH RANGE.
```

FIGURE 25c. Condition Screen With Two Conditions Selected.

After entering the desired equality or inequality symbol in the test condition, enter the date to be used for the comparison. After you have completed building the conditions, the computer asks if you are satisfied with the above condition. If you answer yes [Y], the condition is added to the Command line. If you answer no [N], the condition is abandoned and the Command line remains the same. The command line is cleared to start again.

When you have entered five conditions or have completed the selection process by entering [00], the system makes a final prompt for your approval (illustrated in Figure 25d). You may execute the command [Y] or cancel [N], but you may not modify it.

```
Command -> LIST Test_id, Reaction, B->test date
 FOR B->Stimulus = 'FAST COOKOFF' .AMD. B->test_date > CTOD("01/01/86")
      [01] TEST ID NUMBER
                                                [14] MUNITION NOMENCLATURE
      [02] DOC SERIAL MUMBER
[03] PART MOMEMCLATURE
                                                [15] MUNITION MODIFICATION
                                                [16] NOW MUNDER
       [04] PART NAME (WARHEAD, FUEB, ETC.)
                                                [17] MALC NUMBER
                                                [19] DATA TYPE (TEST OR AMALYSIS)
[20] TEST STIMULUS
       [05] PART TYPE (ADAPTER, IMERT, ETC.)
       [06] EXPLOSIVE LOAD
       07] EXPLOSIVE LOAD WEIGHT
                                                [21]
                                                     TEST DATE
                                                     PROCEDURE
                                                [23] EASARDOUS
       09] TIME TO REACTION
                                                                 PRAGMENTS
       10] METRIC WEIGHT
                                                [24]
                                                     RATIONAL/COMMENT
       11] TOP DRAWING NUMBER
                                                [25] BASELINE TEST
           SPEC MUMBER
                                                     STANDARD TEST
      [13] NUMITION MAKE
                                                [27] IMRT DOCUMENT
                  ARE YOU READY TO EXECUTE THE COMMAND [Y/N] 22
```

FIGURE 25d. Condition Screen With Final Approval Prompt.

Practice Example		
1) Type: <b>Y</b>	Prompt: Are you ready to execute the command (Y/N)?	
	When the listing is completed, the system returns to the List or Locale screen.	

When you follow this Practice Example, execution of the commands will generate a list of test 1D numbers and test dates of all fast cookoff tests on file that occurred after 1 January 1986 (Figure 26).

<b>R</b>	ecord# 6 7 8 4 1 2 3 5	BBFI-01P HNSD-01P HNSD-01P RESC-01W RMFC-01P RMFC-01P RMFC-01P	SYNPATHET	IMPACT PIC DETON PIC DETON PICOFF PIC	 B->TEST_D1 10/20/89 08/08/88 08/08/88 05/29/89 04/05/88 04/05/88 04/05/88	ATB

FIGURE 26. Sample Listing of Pseudo Information.

This concludes the Practice Example. The options and associated screens used were:

(L) List or Locate

[1] List to Screen

Field Selection

List

Condition-building (developing the Command line)

When you select the List to Printer option, you will follow the same procedure shown on page 39, except you will enter [2] instead of [1] at the List or Locate Screen.

## [3] - Locate a Record

This section describes how to use the [3] Locate a Record option. The procedure for setting conditions is similar to that used for the list options [1] or [2] (page 39).

When a [3] I water Record command is selected, the system starts at the top of the file and locates the first occurrence of a record that meets the specified command. The search is done through the Component file; therefore, if more than one component of a single test is found that meets all conditions set, the same test ID number will be displayed for each occurrence.




FIGURE 27. List or Locate Screen.

Practice Example	Prompts/Comments
1) Type: 3	Prompt: Enter your selection (1,2,3 or 4).
	The Field Selection screen will appear.

Field Selections for Locate Option. First you select a field; then you set its conditions. The screen continues to appear and the Command line will build as you set a additions until you have entered five selections or you end the selection processs by entering tellor[0] < RETURN >. Computer prompts guide your selections.

```
Command -> LOCA
       [01] TEST ID NUMBER
                                                    [14] MUNITION MOMENCLATURE
       [02] DOC SERIAL NUMBER
[03] PART NOMENCLATURE
                                                    [15]
                                                         MUNITION MODIFICATION
                                                         MEN MUNBER
                                                    [16]
       [04] PART MAME (WARREAD, FUSE, ETC.)
                                                    [17]
                                                    [17] MALC MUMBER
[19] DATA TYPE (TEST OR AMALYSIS)
            PART TYPE (ADAPTER, IMERT, ETC.)
       [05]
       [06] EXPLOSIVE LOAD
                                                    [20] TEST STINULUS
       [07] EXPLOSIVE LOAD WEIGHT
                                                    [21]
                                                         TEST DATE
       [08]
            COMPONENT REACTION
                                                    [22] PROCEDURE
       (09) TIME TO REACT!
[10] METRIC WEIGHT
             TIME TO REACTION
                                                         MARARDOUS
                                                                      PRAGMENTS
                                                    [23]
                                                         RATIONAL/CONNENT
                                                    [24]
       [11] TOP DRAWING MUMBER
                                                    [25]
                                                         BASELINE TEST
       [12] SPEC NUMBER
                                                         STANDARD TEST
                                                    [27] IMET DOCUMENT
       [13] NUNITION MAKE
          ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET CONDITIONS
FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS.
```

FIGURE 28a. Field Selection Screen for Locate a Record Option.

The Practice Examples explain what to do, step by step, and the illustrations show the results.

Practice Example	Prompts/Comments
1) Type: 18	Prompt: Enter from 1 to 5 fields to which you wish to set conditions for your command. Enter a [0] to end your selections. 0
	Message: Test Date
2) Type: <	Prompt: Enter [<], [<=], [>], [>=], [=] or [#] to select a search range.
3) Press < RETURN >	Message: Test Date <
4) Type: 01/01/90	Message: Test Date < 01/01/90
5) Type. <b>Y</b>	Prompt: Are you satisfied with the above condition $[Y/N]$ ?
	The condition appears on the Command line.

Setting Conditions for Locate Option. You are limited to five conditions. As you enter the number next to the field descriptor, the field name appears in an inverse video area at the bottom of the screen. Figures 28b and 28c show the changing screen, and Figure 28d shows the conditions set on the Command line, as you follow the Practice Example.

```
Command -> LOCA
      [01] TEST ID NUMBER
                                               [14] MUNITION NONENCLATURE
                                               [15] MUNITION MODIFICATION
      [02] DOC_SERIAL NUMBER
      [03] PART NOMENCLATURE
                                               [16] NOW MUKBER
                                               [17] NALC NUMBER
       [04] PART MAME (WARREAD, FUSE, ETC.)
      [05] PART TYPE (ADAPTER, INERT, ETC.)
[06] EXPLOSIVE LOAD
                                               [19] DATA TYPE (TEST OR ANALYSIS)
                                               [20] TEST STINULUS
       [07] EXPLOSIVE LOAD WEIGHT
                                               [21] TEST DATE
       [08] COMPONENT REACTION
                                               [22] PROCEDURE
                                               [23] EASARDOUS
       [09] TIME TO REACTION
                                                                PRAGMENTS
       [10] METRIC WEIGHT
                                               [24] RATIONAL/CONNENT
       [11] TOP DRAWING NUMBER
                                               [25] BASELINE TEST
       [12] SPEC NUMBER
                                               [26] STANDARD TEST
       [13] NUNITION NAME
                                               (27) INST DOCUMENT
         ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET CONDITIONS
         FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 21
                 TEST DATE
     ENTER \{<\}, \{<=\}, \{>\}, \{>=\}, \{=\} or \{\} TO SELECT A SEARCH RANGE.
```

FIGURE 28b. Locate Screen With Enter Test Date Equality or Inequality Prompt.

```
Command -> LOCA
                                                 [14] MUNITION MOMENCLATURE
      [01] TEST ID NUMBER
       [02] DOC_SERIAL MUMBER
                                                 [15] MUNITION MODIFICATION
       [03] PART MOMENCLATURE
                                                 [16] NSW MUNBER
       [04] PART MAME (WARHEAD, FUSE, ETC.)
                                                 [17] MALC MUMBER
      [05] PART TYPE (ADAPTER, IMERT, ETC.)
                                                 [19] DATA TYPE (TEST OR ANALYSIS)
                                                 [20] TEST STIMULUS
       [06] EXPLOSIVE LOAD
       [01] EXPLOSIVE LOAD WEIGHT
                                                 [21] TEST DATE
           COMPONENT REACTION
                                                 [22] PROCEDURE
       [80]
                                                 [23] HABARDOUS
                                                                  PRAGNENTS
       [09] TIME TO REACTION
                                                 [24] RATIONAL/CONCENT
           METRIC WEIGHT
                                                 [25] BASELINE TEST
           TOP DRAWING NUMBER
       [12] SPEC NUMBER
                                                 [26] STANDARD TEST
       (13) NUNITION NAME
                                                 [27] IMRT DOCUMENT
          ENTER FROM 1 TO 5 FIELDS TO WHICE YOU WISE TO SET CONDITIONS
FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 21
                  TEST DATE < 01/01/90
     LHTER [<],[<=],[>],[>=],[=] Or [#] TO SELECT A SEARCH RANGE.
```

FIGURE 28c. Locate Screen With "Less Than 1 January 1990" Entered.

```
COMMANS -> LOCA
 FOR B->test_date < CTOD("01/01/90")
       (01) TEST ID NUMBER
                                                      [14] MUNITION NOMENCLATURE
       [02] DOC_SERIAL MUNBER
[03] PART MOMENCLATURE
[04] PART MAME (WARMEAD, FUEE, ETC.)
[05] PART TIPE (ADAPTER, IMERT, ETC.)
                                                      [15] MUNITION MODIFICATION
                                                      [16] NON NUKBER
                                                      [17] MALC NUMBER
[19] DATA TYPE (TEST OR ANALYSIS)
                                                      [20] TEST STINULUS
[21] TEST DATE
       OS EXPLOSIVE LOAD
       [07] EXPLOSIVE LOAD WEIGHT
       [08] COMPONENT REACTION
                                                      [22] PROCEDURE
       [09] TIME TO REACTION
                                                      [23] HABARDOUS FRAGMENTS
       (10) METRIC WEIGHT
                                                      [24] RATIONAL/CONNENT
                                                      [25] BASELINE TEST
[26] STANDARD TEST
       (11) TOP DRAWING NUMBER
       [12] SPEC NUMBER
       EMAN NOITINUM [21]
                                                      [27] INST DOCUMENT
          ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO ART CONDITIONS
           FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 0
```

FIGURE 28d. Locate Screen With One Condition Selected.

The system continues in the Locate option for you to select more fields (Figure 29). The illustration shows that [20], Stimulus, has been selected.

```
Command -> LOCA
 FOR B->test_date < CTOD("01/01/90")
       [01] TEST ID NUMBER
                                                  [14] MUNITION NOMENCLATURE
                                                  [15] MUNITION MODIFICATION
[16] MSN NUMBER
[17] MALC NUMBER
       [02] DOC_SERIAL NUMBER
       [03] PART MOMENCLATURE
       [04] PART NAME (WARERAD, FUSE, ETC.)
[05] PART TYPE (ADAPTER, YMERT, ETC.)
                                                  [19] DATA TYPE (TEST OR ANALYSIS)
[20] TES'. STINULUS
       [06] EXPLOSIVE LOAD
                                                   [21] TEST DATE
       [07] EXPLOSIVE LOAD WEIGHT
       [08] COMPONENT REACTION
                                                   [22] PROCEDURE
       [09] TIME TO REACTION
                                                   [23] MASARDOUS FRACKENTS
       [10] METRIC WEIGHT
                                                   [24] RATIONAL/CONCENT
       [11] TOP DEAWING MUMBER
                                                   [25] BASELINE TEST
                                                   [26] STANDARD TEST
       [12] SPEC MUMBER
       ELLE MOITING [21]
                                                   [27] IMET DOCUMENT
                     B->Stimulus ?
           WOULD YOU LIKE TO SEE THE LIST OF EXISTING FIELD ENTRIES [Y/N]
```

FIGURE 29. Field Selection Screen for Locate a Record Option.

Practice Example	Prompts/Comments
1) Type: 20	Prompt: Enter from 1 to 5 fields to which you wish to set conditions for your command.
The area of inverse video guides your entry.	Message: B->Stimulus ?
2) Type: Y	Prompt: Would you like to see the list of existing field entries [Y/N] ?
	The list of stimuli appears on the screen.

BULLET IMPACT

BULLET IMPACT

SLOW COORDER

SYMPATERIC DETONATION

B->Stimulus = FAST COORDER

ARE YOU SATISFIED WITH THE ABOVE CONDITION (Y/M)
A REPLY OF (Y) ES WILL ADD THE ABOVE CONDITION TO THE CONDIAND.

FIGURE 30. List of Stimuli.

Follow the Practice Example to select the stimulus.

If you already know what you want, this list can be by-passed by responding [N].

Ĩ	Practice Example	Prompts/Comments	
	e area of inverse video ides your entry	Message: B->Stimulus ?	
1)	Type: Fast Cookoff	A Section 1985	, =
2)	Press < RETURN >		
3)	Type: •	Message: B->Stimulus = Fast Cookoff	
4)	Type. Y	Prompt: Are you satisfied with the above condition $[Y/N]$ ?	e
5)	Туре: 00	The condition appears on the Command line.	
6)	Type: Y	Prompt: Are you ready to execute the command [Y/N] ?	•

Figure 31a shows that a record is found that meets the conditions set, and the computer asks if you want to view the entire record (Y/N). The illustration also shows the completed Command line.

```
COMMENT -> LOCA
 FOR B->test_date < CTOD("01/01/90") .AMP. B->Stimulus = 'FAST COOKOFF'
                                             (14) MUNITION MONENCLATURE
           TEST ID WUNCER
           DOC SERIAL MUMBER
                                             [15]
                                                 MUNITION MODIFICATION
           PART MOMENCLATURE
                                                  NEW MUNBER
           PART MAME (WAPHEAD, FUEE, ETC.)
                                                 MALC MUMBER
                                             [17]
           PART TYPE (ADAPTER, INTRT, ENG.)
                                             [19] DATA TYPE (TROT OR AMAINSIS)
           BIPLOSIVE LOAD
                                             (20j
                                                  TEST STIMULUS
           EXPLOSIVE LOAD WEIGHT
                                                  TRET DATE
           COMPONENT REACTION
                                                  PROCEDURE
           MOITDANK OF CHIT
                                                  REPORT
           METRIC WEIGHT
           TOP DRAWXING MUNIETR
           SPEC NUMBER
           NUMITION MAKE
                                                 IMET DOCUMENT
```

FIGURE 31a. Condition Screen, Conditions Set.

	Practice Example	Prompts/Comments
1)	Type: Y	Prompt: Do you wish to view the entire record of test data [Y/N] ?
		The test record will appear on the screen.

If you want to print the record, you must return to the Main Menu and select the Print or View option (refer to page 29).

Notice in Figures 31b and 31c the identifiers at the top of the screen that tell which screen is displayed, how many tests there are in the file, and which test is now displayed. You can move among the test screens but you can't change tests. You must exit [£], at which time you are asked if you wish to continue the Locate command (Figure 31c). A yes [Y] response will continue the locate process, the system searches for the next record that meets the specified conditions. A no [N] response exits the option and returns the system to the List or Locate screen.




FIGURE 31b. Test Data Screen 1 of 7 Screens.

Review Status: CW Test Screen 1 of 4 Doc\_serial: \$805100 Test\_id Number: RMFC-01P Munition Momen: ME-12 Munition Mune: ROCKET MOTOR Munition Type: MISSILE Munition Hod: WASWIMDER MSH #: MALC #1 Video Project Number: Stimulus: FAST COOKOFF Test Number: CC4-133 Test or Analysis: TEST Test Date: 04/05/88 Procedure: MIL-STD-4040 Standard Test: Y Procedure: DO YOU WANT TO CONTINUE THE LOCATE CONDIAND [Y/N]

FIGURE 31c. Locate Continuation Prompt.

Practice Example	Prompts/Comments
1) Type: Y	Prompt: Do you want to continue the locate command [Y/N] ?
	The system will search for another record that meets the set conditions

If you respond no [N], the List or Locate option screen will appear.

## [9] - Time to Reaction

This section guides you through the selection of another condition that is treated as a special case: [09] Time to Reaction. The process begins by your selecting the [3] Locate a Record option on the List or Locate screen (Figure 32).




FIGURE 32. List or Locate Screen.

Practice Example	Prompts/Comments		
1) Type: <b>3</b>	Prompt: Enter your selection (1,2,3 or 4).		
	The Locate option screen will appear.		

```
Command -> LOCA
                                                 [14] MUNITION MONENCLATURE
      [01] TEST ID NUMBER
                                                 [15] MUNITION MODIFICATION
       [02] DOC_SERIAL NUMBER
       [03] PART MONEMCLATURE
                                                 [16]
                                                      MAN NUMBER
       [04] PART MAKE (WARHEAD, FUEE, ETC.)
                                                 [17] MALC MUMBER
                                                 [19] DATA TYPE (TEST OR ANALYSIS)
      [05] PART TYPE (ADAPTER, IMERT, ETC.)
       [06] EXPLOSIVE LOAD
                                                 [20] TEST STIMULUS
       [07] EXPLOSIVE LOAD WEIGHT
                                                 [21] TEST DATE
       08 COMPONENT REACTION
                                                 [22] PROCEDURE
       091 TIME TO REACTION
                                                 [23] HASARDOUS
                                                                  PRAGNENTS
                                                      RATIONAL/COMMENT
       1101 METRIC WEIGHT
                                                 [24]
           TOP DRAWING NUMBER
                                                 [25] BASELINE TAST
                                                 [26] STANDARD TEET
       [12] SPEC NUMBER
      [13] NUMITION MAKE
                                                 [27] IMET DOCUMBERS
          ENTER FROM 1 TO 5 FIELDS TO WHICE YOU WISH TO SET CONDITIONS
FOR YOUR COMMAND. ENTER A [0] TO EMD YOUR SELECTIONS.
```

FIGURE 33. Locate Option Screen.


Figure 34a shows the Condition screen. Computer prompts guide your selections, and areas of inverse video guide your entries. The Practice Exercises explain what to do, step by step.

```
Command -> LOCA
                                                   [14] MUNITION MONBMCLATURE
       [01] TEST ID NUMBER
       [02] DOC_SERIAL NUMBER
                                                   [15] NUMITION MODIFICATION
       [03] PART MOMENCLATURE
                                                   (16) MSM MUMBER
       [04] PART HAME (WARERAD, FUSE, STC.)
[05] PART TIPE (ADAPTER, IMERT, ETC.)
[06] EXPLOSIVE LOAD
                                                   [17]
                                                        MALC NUMBER
                                                   [19] DATA TYPE (TEST OR AMALYSIS)
                                                        TEST STINULUS
                                                   [20]
       [07] MEYLOSIVE LOAD WEIGHT
                                                   [21]
                                                   [22] PROCEDURE
       [08] COMPONENT REACTION
            TIME TO REACTION
                                                        EASARDOUS
                                                                     PRAGNENTS
                                                        RATIONAL/CONNENT
       101 METRIC WEIGHT
                                                        BASELINE TEST
STANDARD TEST
            TOP DRAWING MUMBER
                                                   [25]
       [12] SPEC NUMBER
                                                        IMBT DOCUMENT
       (13) NUNITION NAME
          ENTER FROM 1 TO 5 FIELDS TO WEICH YOU WISH TO SET COMDITIONS
          FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 9
          TIME TO REACTION
      EMTER \{<\}, \{<=\}, \{>\}, \{>=\}, \{=\} or \{\emptyset\} to select a search range.
```

FIGURE 34a. Condition Screen for Locate Option.

Practice Example	Prompts/Comments
1) Type: <b>09</b>	Prompt: Enter from 1 to 5 fields to which you wish to set conditions for your command. Enter a [0] to end your selections.
2) Type: >	Message: Time to Reaction
3) Press < RETURN >	Message: Time to Reaction >
4) Type: 00:00:30	Message: 00:00:30

The Condition screen continues to appear and the area of inverse video changes as you enter conditions (Figures 34b).



#### FIGURE 34b. Condition Selected.

Practice Example	Prompts/Comments
1) Type: <b>Y</b>	Prompt: Are you satisfied with the above condition $[Y/N]$ ?
	The condition appears on the Command line.

The Time to Reaction > 00:00:30 appears in the area of inverse video in Figure 34b. It will be set and appear on the Command line when you answer [Y] to the computer prompt. Figure 34c shows the screen after you have set the command.

```
Command -> LOCA
 FOR Reacttime >
          TEST ID MUMBER
                                             [14] MUNITION MOMENCLATURE
      1021 DOC SERIAL MUMBER
                                             [15] NUNITION MODIFICATION
      [03]
          PART MOMENCLATURE
                                                  MSH NUMBER
                                             [16]
          PART MAKE (WARHEAD, FUSE, ETC.)
                                             [17] MALC MUMBER
      1041
      [05] PART TYPE (ADAPTER, IMERT, ETC.)
                                             [19] DATA TYPE (TEST OR AMALYSIS)
          EXPLOSIVE LOAD
                                             [20]
                                                  TEST STIMULUS
      07] EXPLOSIVE LOAD WEIGHT
                                                  TEST DATE
          COMPONENT REACTION
                                                  PROCEDURE
          TIME TO REACTION
                                                  MASARDOUS
                                                             PRAGMENTS
          METRIC WEIGHT
                                                  RATIONAL/COMMENT
       101
                                             [24]
          TOP DEAWING MUMBER
                                                  BASELIME TEST
                                             [25]
          SPEC NUMBER
                                                  STANDARD TEST
      [13] NUNITION NAME
                                             [27] INST DOCUMENT
         EMTER TROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET COMDITIONS
         FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 00
```

FIGURE 34c. Condition Appears on Command Line.

Practice in the Locate a Record option continues in the next section.

### [8] - Component Reaction

This section guides you through the selection of |08| Component Reaction. Figure 35a shows the *Condition* screen; Figure 35b is the *Value* screen. The Practice Exercises explain what to do, step by step.

```
CORMAND -> LOCA

[01] TEST ID NUMBER
[02] DOC SERIAL NUMBER
[03] PART NOMEMCLATURE
[04] PART NAME (BOOSTER, FURE, ETC.)
[05] PART TIPE (ADAPTR, FURE, ETC.)
[06] EXPLOSIVE LOAD
[07] EXPLOSIVE LOAD
[07] EXPLOSIVE LOAD (INTEST STIMULUS
[08] COMPONENT REACTION
[19] PROCEDURE
[09] TIME TO REACTION
[10] METRIC WEIGHT
[10] METRIC WEIGHT
[10] METRIC WEIGHT

ENTER FROM 1 TO 5 FIRLDS TO WHICH YOU WISH TO SET CONDITIONS
FOR YOUR COMMAND. ENTER A [0] TO END YOUR SELECTIONS. 0
```

FIGURE 35a. Condition Screen for Locate Option.

Practice Example	Prompts/Comments	
1) Type: <b>08</b>	Prompt: Enter 1 to 5 fields to which you wish to set conditions for your command. Enter a [0] to end your selections.	
	The Value Selection screen will appear.	

Below are listed the reactions encountered in this information center.
They are listed in descending order of severity with "DETONATION"
counted as the most severe case and "MO TEST" counted as the least.

DETOMATION # 10

SYMPATHETIC DETONATION # 9

EXPLOSION # 7

DEFLAGRATION # 6

UNDETERMINED # 5

BURNING # 4

MO SYMPATHETIC DETONATION # 3

MO REACTION # 2

MO REACTION # 2

ENTER THE VALUE ASSIGNED TO THE REACTION YOU WISH TO SEARCE FOR -> 00

FIGURE 35b. Value Selection Screen.

Classes of Reactions. The Value Selection screen displays the classes of reactions dealt with in this system. You are first prompted to enter the level of reaction that will be used in the comparison condition. Figure 35c is an example for selection of |04| Burning. As you follow the Practice Example, the area of inverse video will change, as shown in Figures 35c and 35d, and the Command line is set as shown in Figure 35e.

Practice Example	Prompts/Comments
1) Type: <b>04</b>	Prompt: Enter the value assigned to the reaction you wish to search for ->
	Message: Burning
2) Type: >	Prompt: Enter [<], [<=], [>], [>=], [=], or [#] to select a search range.
3) Press < RETURN >	Message: > Burning
3)	Prompt: Are you satisfied with the above condition [Y/N] ?
	The condition appears on the Command line of the Condition screen.

Below are listed the reactions encountered in this information center. They are listed in descending order of severity with "DETONATION" counted as the most severe case and "NO TEST" counted as the least.

DETOMATION = 10 SYMPATERTIC DETONATION = 9 EXPLOSION \_ . PROPULSION . 7 DEFLAGRATION UNDETERMINED 5 RITENTNO = MO SYMPATHETIC DETONATION = 3 MO REACTION = 2 MO TEST

ENTER THE VALUE ASSIGNED TO THE REACTION YOU WISE TO SEARCH FOR ->

Reaction > BURNING

ARE YOU SATISFIED WITH THE ABOVE COMDITION (Y/N) ??

FIGURE 35c. Value Screen Prior to Use of "Enter" < RETURN > Key.

Command -> LOCA FOR Reacttime > "00:00:30" .AMD, reaction > BURNING

[14] NUNITION MOMENCLATURE [15] NUNITION MODIFICATION [01] TEST 1D NUMBER [02] DOC SERIAL NUMBER [03] PART MOMENCLATURE [16] NOW MUNDER [04] FART HOMESCLATURE
[04] FART HAME (WARHEAD, FUSE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
[06] EXPLOSIVE LOAD
[07] EXPLOSIVE LOAD WEIGHT
[08] COMPONENT REACTION [17] NALC NUMBER [19] DATA TYPE (TEST OR ANALYSIS) [20] TEST STINULUS [21] TEST DATE [22] PROCEDURE [23] HABARDOUS FRAGMENTS [09] TIME TO REACTION [10] METRIC WEIGHT [24] RATIONAL/CONNENT [11] TOP DRAWING NUMBER [25] BASELINE TEST [26] STANDARD TEST [27] INST DOCUMENT [12] SPEC NUMBER [13] MUNITION MAKE

ENTER FROM 1 TO 5 FIELDS TO WHICH YOU WISH TO SET CONDITIONS FOR YOUR CONMAND. ENTER A [0] TO END YOUR SELECTIONS.

FIGURE 35d. Value Screen After Selection Confirmed With "Enter" Key and Prior to Final Confirmation.

```
Command -> LOCA
FOR Reacttime > '00:00:30' .AMD. reaction > BURMING
                                                    [14] NUMITION MOMENCLATURE
       [01] TEST ID NUMBER
       [02] DOC_SERIAL MUMBER
                                                    [15] MUNITION HODIFICATION
       [03] PART MOMENCLATURE
[04] PART MAME (WARREAD, FUSE, ETC.)
[05] PART TYPE (ADAPTER, IMERT, ETC.)
[06] EXPLOSIVE LOAD
                                                    [16] NON NUMBER
                                                    [17] NALC NUMBER
                                                    (19) DATA TYPE (TEST OR ANALYSIS)
(20) TEST STINULUS
       [07] EXPLOSIVE LOAD WRIGHT
                                                    [21] TEST DATE
       [08] COMPONENT BRACTION
                                                    [22] PROCEDURE
       [09] TIME TO REACTION
                                                    [23] HAMARDOUS
                                                                      FRAGMENTS
       [10] METRIC WEIGHT
                                                         RATIONAL/COMMENT
                                                    [24]
       [11] TOP DRAWING MUMBER
                                                    [25] BASELINE TEST
                                                    [26] STANDARD TEST
       [12] SPEC MUMBER
       [13] NUNITION NAME
                                                    [27] INRT DOCUMENT
                   ARE YOU READY TO EXECUTE THE CONMAND [Y/N]
```

FIGURE 35e. Reaction Value Appears on Command Line of Condition Screen.

When selections have been completed, the screen remains the same, but another prompt appears. Follow the Practice Example to continue the Locate option.

Practice Example	Prompts/Comments
1) Type: Y	Prompt: Are you ready to execute the command [Y/N] ?
2) Type: 00	The Viewing screen will appear.

```
Command -> LOCA
FOR Reacttime > '00:03:00' .AMD. reaction > BURNING
                                             [14] MUNITION NOMENCLATURE
      [01] TEST ID NUMBER
      [32] DOC_SERIAL MUMBER
                                             [15] MUNITION HODIFICATION
      [03] PART MOMENCLATURE
                                             [16]
                                                  MSM MUMBER
      [04] PART MAME (WARHEAD, FUSE, ETC.)
                                                  MALC MUMBER
                                             [17]
      [05] PART TYPE (ADAPTER, IMERT, STC.)
                                                  DATA TYPE (TEST OR ANALYSIS)
                                             [29]
      [06] EXPLOSIVE LOAD
                                                  TEST STIMULUS
                                             f201
      [07] EIPLOSIVE LOAD WEIGHT
                                             [31]
                                                  TEST DATE
      [08] COMPONENT REACTION
                                                  PROCEDURE
      [09] TIME TO REACTION
                                                  HARARDOUR
                                                             PRAGNENTS
                                             1231
      [10] METRIC WRIGHT
                                                  RATIONAL/COMMENT
      [11] TOP DRAWING MUMBER
                                             [25] BASELINE TEST
      [12] SPEC NUMBER
                                             [24] STANDARD TEST
      EMAN MOITINUM [11]
                                             [27] IMRT DOCUMENT
         TEST_ID
Records
         BRIC-03A
           DO YOU WISH TO VIEW THE ENTIRE RECORD OF TEST DATA [Y/N] 878
```

FIGURE 36a. Locate Screen With View Prompt.

Practice Example	
1) Type: <b>Y</b>	Prompt: Do you wish to view the entire record of test data (Y/N) ?
	The test records will be displayed on the screen.

The system will execute the command, shown at the top of the screen, to locate the first record of a component that had a reaction more severe than <u>burning</u> that occurred after <u>30 seconds</u>. The test ID number of the test record found is shown at the bottom of the screen in Figure 36a.

After the command is executed, the test II) number of the first record found that meets the specified conditions is displayed (Figure 36b), and you are given the option of viewing the test.

The identifiers at the top of the screen tell which screen is displayed, how many tests there are in the file, and which test is now displayed. You can move among the test screens (forward [F] or backward [B], but you can't change tests. Figure 35° is the final screen. To find another test you must exit [E] and return to the *List or Locate* screen.

Review Status: 7 Test Screen 1 of 4 Test 1 of 7 Doc serial: 8504700 Test\_id Number: BRFC-03A Munition Momen: MK 82 Munition Mane: BRAG Munition Type: MISSILE Munition Mod: MBN 4: AALC #: Video Project Number: Stimulus: FAST COOKOFF Test Number: SEC 12-11 A Test or Analysis: TEST Test Date: 04/26/84 Procedure: MIL-STD-1648A(AS) Baseline Test: Y Standard Test: M IMRT Document: n Procedures THE TIME TO 1000 F FLAME TEMP WAS 140 SEC. Do you wish to change screens (F) orward, (B) ackward or (E) mit to assist 27

FIGURE 36b. Test Screen 1 of 4 Screens, Test Data.

Screen 4 of 4
Test Data Reference for Test\_id number BRFC-03A
Document Classification : U

Doc Title : BRAG AIR VEHICLE DEVELOPMENT TEST PROPLUSION AND ORDNANCE SAFETY TEST REPORT

Report No. : MAVAIR 32050-351 MA Report Date : 04/01/85 Report Status : FIMAL

leport Status : FINAL INST (Y/W):

Point of Contact (Mame, Agency , Phone)
WILL BOX, MAVAIR, AUTO PARK, CA. 619-371-2830

Document Serial Number : 8504700

From here, you may change screens [3]ackward to the component data, or you may change screens [7]orward to the first screen of this test. Do you wish to change screens (7)orward, (8)ackward or (8)xit to assist

FIGURE 36c. Test Screen 4 of 4 Screens, Documentation Data.

When you have finished viewing the data and enter [E], a prompt asks if you want to continue the Locate command. When you respond yes [Y], the system will look for the next record with the conditions you have set. If the system does not find a record meeting the set condition, you are so informed and the system returns to the *List or Locate* menu.

This concludes the discussion and presentation of Practice Examples.

#### SUMMARY

The MSIC allows you to view, manipulate, and print data in selected formats. A program that prints a summary of all testing recorded in the databases or of tests conducted with a specific weapon is planned.

#### CONCLUSIONS

Steady use of the preliminary MSIC database for more than three years has shown it to be a valuable tool for the insensitive munitions community. It was released for distribution at end of fiscal year 1989. Releasing authority lies with the Naval Sea Systems Command (NAVSEA-662), Washington, D.C. 20362-5101.

Two insensitive munitions databases are scheduled for release for the

#### OTHER NIMIS DATABASES

# INSENSITIVE MUNITIONS ENGINEERING TECHNOLOGY (IMET)

This database will allow you to view, manipulate, and print generic insensitive munitions (IM) advanced development technology methods and testing data in a manner similar to the MSIC.

Screens display the technology concept, such as preferential insulation technique (PIT), thermite case penetrator (TCP), or thermally activated safe/arm device (TASAD), applicable weapons, problem under consideration, IM stimulus to be addressed, test data, test item configuration and energetic materials, and reference document(s). The IMET has been programmed, but not yet released.

The MET database can be manipulated in a manner similar to the MSIC and will be as simple—t simpler, for the layman to use. None of the databases, either operational or planned, will require computer literacy to operate.

The IMET, soon to be operational, will expand the scope of available data to include insensitive munitions advanced development data relating to generic IM concepts under development at various laboratories.

# ENERGETIC MATERIALS INFORMATION CENTER (EMIC)

The EMIC programming effort is under way as of this printing. The purpose of the EMIC is to make energetic materials data, such as that found in the Navy Explosives Handbook (Reference 9), easily accessible and manipulable. It will include IM and performance-related data on high explosives, propellants, and pyrotechnics.

When completed by incorporation of the IMET, FMCIS, and EMIC, the NIMIS will provide a useful tool to all of the IM community, from those engaged in energetic material research through weapon designers and developers to project and program managers.

#### REFERENCES

- 1. Office of the Chief of Naval Operations. U.S. Navy Policy on Insensitive Munitions. Washington, D.C., CNO, 13 May 1984. (OPNAVINST 8010.13, publication UNCLASSIFIED.)
- 2. Naval Sea Systems Command. Technical Requirements for Insensitive Munitions. Washington, D.C., NAVSEASYSCOM, 22 May 1985. (NAVSEAINST 8010.5, publication UNCLASSIFIED.)
- 3. Office of the Chief of Naval Operations. U.S. Navy Policy on Insensitive Munitions. Washington, D.C., CNO, 27 June 1989. (OPNAVINST 8010.13B, publication UNCLASSIFIED.)
- 4. Naval Sea Systems Command. Technical Requirements for Insensitive Munitions. Washing on, D.C. NAVSEASYSCOM, 5 December 1989. (NAVSEAINST 8010.5B, publication 'INC! SIFIED.)
- 5. Naval Air Systems Command. Criteria and Test Procedures for Ordnance Exposed to an Aircraft Fuel Fire. Washington, D.C., NAVAIRSYSCOM, 30 September 1982. (MIL-STD-1648A(AS), publication UNCLASSIFIED.)
- 6. Department of Defense. Hazard Assessment Tests for Navy Non-Nuclear Ordnance. Washington, D.C., DOD, 9 September 1982. (DOD-STD-2105, publication UNCLASSIFIED.)
- 7. Naval Weapons Center. Standard Procedures for Conducting the Multiple Fragment Impact (FRAGMAT) Test ("For Score"), by J. L. Stotser. China Lake, Calif., NWC, December 1988. (NWC TM 6811, publication UNCLASSIFIED.)
- 8. Department of Defense. Military Standard, Hazard Assessment Tests for Non-Nuclear Ordnance. Washington, D.C., DOD, 19 January 1990. (MIL-STD-2105A (NAVY) (Draft), publication UNCLASSIFIED.)
- 9. Naval Surface Weapons Center. Navy Explosives Handbook. White Oak, Md., NSWC, 1988. (NSWC MP 88-116, publication UNCLASSIFIED.)

#### INITIAL DISTRIBUTION

# ON CENTER DISTRIBUTION

1 Code 01 1 Code 31 1 Code 32 4 Code 343 (3 plus Archives Copy) 1 Code 38 40 Code 3208, C. Dettling